



**COLE SOFTWARE, LLC**

736 Fox Hollow Road • Afton, VA 22920

540-456-8210 • 540-456-6658: FAX

INTERNET: <http://www.colesoft.com>

E-MAIL: [cswtech@colesoft.com](mailto:cswtech@colesoft.com)

**z/XDC®  
INSTALLATION GUIDE**

**z/XDC® Release z1.2 for z/OS  
(and OS/390)**

David B. Cole

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **PREFACE**

### **PROPRIETARY LEGEND**

z/XDC® and its documentation (collectively, "Product"), including copies thereof, are the confidential and proprietary property of Cole Software, LLC ("Owner"). Product may be used only by those organizations that are licensed by Owner for such use and only in the manner so licensed. The program and documentation may not be published, reproduced, distributed, or made available to third parties for any purpose without the expressed written permission of Owner; however, a reasonable number of copies may be made of the documentation (including the copyright notices and proprietary legends thereon) as is necessary for the legitimate use of Product within a licensed organization.

Except as may be otherwise expressed in a signed agreement between Owner and Customer, Owner makes no representations or warranties, expressed or implied, including, but not limited to, the implied warranties of merchantability and fitness for a particular purpose, the warranty of freedom from rightful claims by way of infringement and the like, and any warranty as to accuracy.

**WARNING!** z/XDC® is a powerful tool for dynamically locating and correcting malfunctions in actively executing user programs and operating system programs and subroutines. Accordingly, it is inherent in its design, that unless the use of this product is properly controlled, then under certain conditions a malicious or careless user can use the product to alter, subvert, counterfeit, damage or otherwise disturb the normal execution of user programs or system routines including, under certain conditions, both its own and system security routines.

Therefore, even if advised of the possibility of loss or damages, under no circumstances shall Owner be liable for any loss or damage whatsoever (including death) arising from Product, whether such loss or damage be direct, indirect, consequential, special or otherwise. Further, Owner shall not be obligated to indemnify any user of Product in any manner for any loss which the user or anyone else may experience, of any kind or nature, arising out of the use or misuse of Product.

### **CONTACTING COLE SOFTWARE**

The **z/XDC®** products are marketed by **COLE SOFTWARE, LLC** with its principal office in Afton, Virginia. If you want more information, please contact COLE SOFTWARE Marketing as follows:

Phone: **800-XDC-5150** or **928-771-2003**  
FAX: **928-771-2005**  
E-Mail: [bshimizu@colesoft.com](mailto:bshimizu@colesoft.com)  
Home Page: <http://www.colesoft.com>

Our Technical Support contacts are:

Phone: **540-456-8210**  
FAX: **540-456-6658**  
E-Mail: [cswtech@colesoft.com](mailto:cswtech@colesoft.com)  
Home Page: <http://www.colesoft.com>  
FTP site: <ftp.colesoft.com>

# ***z/XDC® z1.2 INSTALLATION GUIDE***

(Preface)

Our Customer Services contacts are:

Phone: **540-456-8210**  
FAX: **540-456-6658**  
E-Mail: [cswstaff@colesoft.com](mailto:cswstaff@colesoft.com)  
Home Page: <http://www.colesoft.com>

Our snail mail address is:

Address: **Cole Software, LLC**  
**736 Fox Hollow Road**  
**Afton, Virginia 22920**  
**USA**

Our home page provides the following services:

- General information about z/XDC.
- E-mail links to both Marketing, Technical Support, and Customer Services.
- FTP links for uploading diagnostic information and other files to Technical Support.
- FTP links for downloading current maintenance for z/XDC.
- Links permitting existing customers to download a full set of z/XDC's documentation.
- An order form for obtaining an upgrade of XDC to its current version (z/XDC) and release (z1.2).

## **TRADEMARKS**

**TFS™**, **XDC-TFS™**, **CDF™**, **XDC-CDF™**, and **FASM™** are trademarks of Cole Software, LLC. **Extended Debugging Controller®**, **XDC®**, **XDC/SE®**, and **z/XDC®** are registered trademarks of Cole Software, LLC. Other brand and product names referenced in this document are trademarks or registered trademarks of their various holders. Use of their names herein is for identification purposes only.

## **ADDITIONAL MANUALS**

z/XDC customers may make as many copies of this manual as they feel is necessary for the legitimate use of z/XDC within their organization. Existing customers may download from our web site ([www.colesoft.com](http://www.colesoft.com)) printable copies of all of z/XDC's manuals. Each manual is available in PDF format.

# ***z/XDC® z1.2 INSTALLATION GUIDE***

**(Preface)**

# ***z/XDC® z1.2 INSTALLATION GUIDE***

(Preface)

## **CONTENTS**

<b>PREFACE</b> .....	<b><u>ii</u></b>
PROPRIETARY LEGEND .....	<u>ii</u>
CONTACTING COLE SOFTWARE .....	<u>ii</u>
TRADEMARKS .....	<u>iii</u>
ADDITIONAL MANUALS .....	<u>iii</u>
<b>CONTENTS</b> .....	<b><u>v</u></b>
<b>FIGURES</b> .....	<b><u>vii</u></b>
<b>THE z/XDC PRODUCT DISTRIBUTION PACKAGE</b> .....	<b><u>1</u></b>
Printing z/XDC's Various Manuals .....	<u>2</u>
Printing the PDF-Formatted Manuals .....	<u>2</u>
Getting the Product Files to Your Mainframe .....	<u>2</u>
Step 1: Transmit the <i>Xdcxmit.trs</i> Files to Your Mainframe .....	<u>2</u>
Step 2: Decompress the XDCXMIT Library .....	<u>3</u>
Step 3: Extract the Installation Libraries from DBCOLE.XDCZ12.INSTALL.XDCXMIT .....	<u>4</u>
<b>INSTALLING THE EXTENDED DEBUGGING CONTROLLER</b> .....	<b><u>7</u></b>
z/XDC z1.2's Compatibility with XDC's Prior Versions/Releases (XDC X3.3 and XDC/SE S2.0) .....	<u>7</u>
Installation Summary .....	<u>8</u>
Pre-SMP/E Phase: .....	<u>8</u>
SMP/E Phase: .....	<u>8</u>
Post-SMP/E Phase: .....	<u>8</u>
Pre-SMP/E Installation Phase .....	<u>9</u>
Step : Choose Naming Conventions for z/XDC's Target, DLIB, and SMP Datasets .....	<u>10</u>
Step : Downloading Maintenance from our Web Site .....	<u>10</u>
Step : Upload the Maintenance to Your Mainframe .....	<u>11</u>
Step : Edit the DBCOLE.XDCZ12.INSTALL.XDCJCL Jobs According to Local Requirements .....	<u>11</u>
Step : Run SMPCSI to Create SMP Datasets for z/XDC .....	<u>12</u>
Step : Run SMPDDDEF to Create z/XDC Target and DLIB Datasets .....	<u>12</u>
SMP/E Installation Phase .....	<u>13</u>
Step : Run the SMPBASE Job .....	<u>14</u>
Step : Run the SMPMAINT Job .....	<u>14</u>
Do not attempt to perform APPLY CHECK! .....	<u>14</u>
Post-SMP/E Installation Phase .....	<u>15</u>
Step : Renaming z/XDC .....	<u>15</u>
Step : Adding z/XDC's Target Libraries to Your System .....	<u>17</u>
Adding XDCPLPA .....	<u>18</u>
Adding XDCLINK .....	<u>18</u>
XDCHELPM: Additional Considerations .....	<u>20</u>
XDCCALLA and XDCCMDA: Additional Considerations .....	<u>20</u>
Adding XDCCLIST .....	<u>21</u>
Adding XDCMLIB, XDCPLIB, and XDCTLIB .....	<u>22</u>
Setting Up the XDCPANEL Panel or the XDCLBDEF Clist .....	<u>24</u>
Choosing Between Installing XDCPANEL Directly or Indirectly via XDCLBDEF .....	<u>25</u>
Adding XDCCMDS .....	<u>26</u>
Step : Re-IPL (Maybe) .....	<u>26</u>
Step : Defining Your License to Use z/XDC .....	<u>26</u>
Step : Defining z/XDC to Your Computer's Security System .....	<u>29</u>
For More Information About z/XDC Security ... ..	<u>29</u>
z/XDC's Standard Security Method .....	<u>30</u>
Using z/XDC Prior to Creating Security Definitions .....	<u>30</u>
Using z/XDC in RACF Protected Systems .....	<u>31</u>
Using z/XDC in CA-ACF2 (Release 5.0 and Newer) Protected Systems .....	<u>33</u>
Using z/XDC in CA-Top Secret Protected Systems .....	<u>35</u>

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Contents)**

Another Approach to z/XDC Security .....	<a href="#">37</a>
Step : Installing z/XDC's Service and Hook SVCs (via the XDCINITc Job) .....	<a href="#">38</a>
What the XDCINITc Job Does .....	<a href="#">39</a>
Running XDCINITc Jobs for Multiple Versions and Releases of XDC .....	<a href="#">39</a>
Running z/XDC Without Its Service and Hook SVCs .....	<a href="#">39</a>
Step : The Installation Verification Test .....	<a href="#">40</a>
Step : Changing the Default MAPLIB Library .....	<a href="#">43</a>
Step : Changing the Default Profile: TFSXDC12 .....	<a href="#">44</a>
How to Change z/XDC's System Wide Default Profile .....	<a href="#">44</a>
Which System Wide Default Profile Values You Might Consider Changing .....	<a href="#">45</a>
Step : Installing z/XDC's Cross Domain Facility (CDF) .....	<a href="#">49</a>
Step : xxxCDF Installation Verification .....	<a href="#">52</a>
Step : Exit Routines .....	<a href="#">53</a>
<b>INSTALLING A DEBUGGING INTERFACE INTO JES2 .....</b>	<a href="#">56</a>
What the XDC/JES2 Interface Is and Does .....	<a href="#">56</a>
The Members of DBCOLE.XDCZ12.XDCJES2 .....	<a href="#">56</a>
Exit 0: The "XDC" Initialization Option .....	<a href="#">57</a>
Exit 5: The "\$XDC" Command .....	<a href="#">57</a>
Exit 5: The "\$PJES2,ABEND" Command .....	<a href="#">58</a>
Debugging JES2 with z/XDC Clones .....	<a href="#">58</a>
Communicating with the XDC/JES2 Interface .....	<a href="#">59</a>
J2IFUPDT: JES2 Csect Mapping Support .....	<a href="#">59</a>
Using JES2 Csect Maps .....	<a href="#">60</a>
Using JES2 Dsect Maps .....	<a href="#">61</a>
Browsing JES2 via Foreign Address Space Mode .....	<a href="#">61</a>
A Browsing Example .....	<a href="#">61</a>
<b>APPENDIX A: CHANGE HISTORY - z/XDC RELEASE z1.2 .....</b>	<a href="#">64</a>
<b>INDEX .....</b>	<a href="#">66</a>

# *z/XDC® z1.2 INSTALLATION GUIDE*

## FIGURES

<b>Figure 1</b>	z/XDC Distribution Package Map .....	<u>1</u>
<b>Figure 2</b>	z/XDC Manuals .....	<u>2</u>
<b>Figure 3</b>	Commercial Workstation Software .....	<u>3</u>
<b>Figure 4</b>	Sample JCL for Decompressing DBCOLE.XDCZ12.INSTALL.XDCXMIT .....	<u>4</u>
<b>Figure 5</b>	z/XDC Installation Libraries .....	<u>5</u>
<b>Figure 6</b>	The SMP/E Datasets Created by the SMPCSI Job .....	<u>12</u>
<b>Figure 7</b>	The Target and DLIB Datasets Created by the SMPDDDEF Job .....	<u>13</u>
<b>Figure 8</b>	Model JCL for Copying z/XDC Load Modules Prior to Renaming Them .....	<u>16</u>
<b>Figure 9</b>	Model JCL for Renaming XDCCALL via Relinkedit .....	<u>16</u>
<b>Figure 10</b>	z/XDC's Load Modules and Their Appropriate Target System Libraries .....	<u>17</u>
<b>Figure 11</b>	Adding XDCCALLA and XDCCMDA to IKJTSOxx .....	<u>21</u>
<b>Figure 12</b>	z/XDC's ISPF Clists, Panels, Tables, and Message Modules .....	<u>23</u>
<b>Figure 13</b>	ISPF Panel Mods for Invoking the XDCPANEL Panel .....	<u>25</u>
<b>Figure 14</b>	z/XDC's License Definition Screen .....	<u>28</u>
<b>Figure 15</b>	RACROUTE Macro Operands Used by z/XDC in <b>RACF</b> Protected Systems .....	<u>32</u>
<b>Figure 16</b>	RACROUTE Macro Operands Used by z/XDC in <b>CA-ACF2</b> Protected Systems .....	<u>34</u>
<b>Figure 17</b>	RACROUTE Macro Operands Used by z/XDC in <b>CA-Top Secret</b> Protected Systems .....	<u>36</u>
<b>Figure 18</b>	XDCINITc PROC and Associated COMMNDxx Command .....	<u>38</u>
<b>Figure 19</b>	z/XDC's Startup Panel in ISPF .....	<u>40</u>
<b>Figure 20</b>	Initial Screen Displayed by z/XDC with Fullscreen Display Support Installed .....	<u>41</u>
<b>Figure 21</b>	Error When z/XDC is Not Properly Installed into ISPF .....	<u>41</u>
<b>Figure 22</b>	Starting z/XDC Authorized from its Startup Panel in ISPF .....	<u>42</u>
<b>Figure 23</b>	Initial Screen Displayed by Authorized Mode z/XDC (with Fullscreen Support Installed) .....	<u>43</u>
<b>Figure 24</b>	z/XDC's Profile Menu System .....	<u>45</u>
<b>Figure 25</b>	Profile Settings for z/XDC's Session Log .....	<u>46</u>
<b>Figure 26</b>	Profile Settings for xxxPRINT Output Files .....	<u>46</u>
<b>Figure 27</b>	Profile Settings for Assigning PF-key Sets to PF-key Numbers .....	<u>47</u>
<b>Figure 28</b>	Default PF-key Definitions .....	<u>48</u>
<b>Figure 29</b>	Typical VTAMLST File for XDC-CDF .....	<u>50</u>
<b>Figure 30</b>	Typical SYSIN File Parameters for XDC-CDF .....	<u>50</u>
<b>Figure 31</b>	Model JCL for the xxxCDF Router Task .....	<u>51</u>
<b>Figure 32</b>	Model JCL for Testing xxxCDF .....	<u>52</u>
<b>Figure 33</b>	Logon Screen for VTAM connections to z/XDC's Cross Domain Facility .....	<u>53</u>
<b>Figure 34</b>	XDC-CDF Job Selection menu .....	<u>53</u>

# ***z/XDC® z1.2 INSTALLATION GUIDE***

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **THE z/XDC PRODUCT DISTRIBUTION PACKAGE**


z/XDC "Product Distribution Packages" can be obtained via the following media or methods:

- CD-ROMs
- E-mail (planned)
- Downloads from our web site: [www.colesoft.com](http://www.colesoft.com) (planned)

A package consists of a compressed file that must be uploaded to the mainframe and then decompressed before the product can be installed via SMP/E.

If you have received z/XDC via CD-ROM, then you will have received the product files organized into a folder structure as shown in [Figure 1](#) on page 1. If you've received z/XDC via the Internet, then you will have received a ZIP'd file containing this same file structure.

- The *Product* folder contains an *xdcxmit.trs* file that will have to be uploaded to your mainframe and then restored to its original format via MVS's TRSMAN program and then TSO's RECEIVE<sup>1</sup> commands.
- The *Documentation - PDF* folder contains all of z/XDC's manuals and other documents in PDF format.<sup>2</sup> The documentation can be searched, read, or printed directly from the CD-ROM or your hard drive using Adobe's Acrobat Reader.



**Figure 1** z/XDC Distribution Package Map

If you have received the product package via the Internet, then you have received a ZIP'd file named *xdcz12.zip*. This package contains the same file structure that you would have received via CD-ROM (see [Figure 1](#) on page 1). You will have to extract the files using PKUNZIP<sup>3</sup>, WinZip<sup>4</sup>, ZTree<sup>5</sup> or whatever decompression tool you prefer.

---

<sup>1</sup>NOT to be confused with SMP/E's RECEIVE command! That's something entirely different.

<sup>2</sup>PDF stands for "Portable Document Format". It is a documentation format that was developed by and is supported by Adobe Systems, Inc. A reader for this format is available without charge from Adobe's web site: [www.adobe.com](http://www.adobe.com). The name of the reader is "The Adobe Acrobat Reader".

<sup>3</sup>PKZIP and PKUNZIP are file compression and decompression programs that are available from [www.pkware.com](http://www.pkware.com).

<sup>4</sup>WinZip is a file compression/decompression utility that is available from [www.winzip.com](http://www.winzip.com).

<sup>5</sup>ZTree is a superb file manager utility that is available from [www.ztree.com](http://www.ztree.com). It includes a comprehensive interface to the compression/decompression utility of your choice.

# ***z/XDC® z1.2 INSTALLATION GUIDE***

(The z/XDC Product Distribution Package)

## **Printing z/XDC's Various Manuals**

z/XDC's documentation consists of the manuals shown in [Figure 2](#) on page [2](#). The manuals are provided in PDF format. This is a good format for both browsing, searching, and printing.

<b>z/XDC z1.2 Manual Name</b>	<b>Description</b>
Release Guide	Describes what is new with release z1.2 of z/XDC.
User's Guide	Explains how to use z/XDC z1.2.
Commands Reference	Describes all of z/XDC z1.2's commands.
Messages Reference	Explains all numbered messages issued by z/XDC z1.2.
Install Guide	Describes how to install z/XDC z1.2 (the current document).

**Figure 2** z/XDC Manuals

## **Printing the PDF-Formatted Manuals**

PDF stands for "Portable Document Format". It is a documentation format that was developed by and is supported by Adobe Systems, Inc. A reader for this format is available without charge from Adobe's web site: [www.adobe.com](http://www.adobe.com). The name of the reader is "The Adobe Acrobat Reader".

To print a z/XDC manual, start up Acrobat Reader and use it to open the desired manual. Note, when you do this, Acrobat may issue the following warning message:

*Unable to find or create the font 'WPTypographicSymbols'. Some characters may not display or print correctly. **OK***

This message occurs because the original z/XDC documents were created using WordPerfect, and Adobe apparently is not licensed to display some of the fonts that WordPerfect automatically uses. Simply press the **OK** button and proceed.

You may be able to correct this "problem" by selecting Acrobat Reader's **View** menu and then making sure that **Use Local Fonts** is checked. If you have WordPerfect installed on your system, this should take care of it.

If checking **Use Local Fonts** does not resolve the problem, then don't bother worrying about it any further. The "display problems" referred to by the warning are not really significant in any case.

## **Getting the Product Files to Your Mainframe**

The distribution package's *product* folder contains three files: *\$readme.txt*, *\$unterse.jcl*, and *xdcxmit.trs*.

- *Xdcxmit.trs* contains the product's installation libraries in tersed xmit-library format.
- *\$unterse.jcl* contains sample JCL for decompressing the xmit-library.
- *\$readme.txt* identifies the release level of the *xdcxmit.trs* file.

Regardless of whether you received z/XDC via CD-ROM or from the Internet, you will now have to upload the product file (*xdcxmit.trs*) to your mainframe and extract the installation libraries from with it. Here's how to do that.

### **Step 1: Transmit the *Xdcxmit.trs* Files to Your Mainframe**

I assume that you are using a PC that is running some sort of "workstation" program that allows you to connect to your mainframe as a 327x type terminal. [Figure 3](#) on page [3](#) shows just a few examples of many such programs.

# ***z/XDC® z1.2 INSTALLATION GUIDE***

(The z/XDC Product Distribution Package)

These programs all have a file transfer capability for sending files back and forth between the mainframe and your PC.

<b>Company</b>	<b>Workstation Product</b>	<b>Web Site</b>
Attachmate	Extra!	<a href="http://www.attachmate.com">www.attachmate.com</a>
Ericom	PowerTerm	<a href="http://www.ericom.com">www.ericom.com</a>
HOB	HOBLink Terminal Edition	<a href="http://www.hobsoft.com/www_us/produkte/connect/term-ed.htm">www.hobsoft.com/www_us/produkte/connect/term-ed.htm</a>
Hummingbird	Host Explorer	<a href="http://www.hummingbird.com">www.hummingbird.com</a>
IBM	Personal Communications	<a href="http://www-3.ibm.com/software/network/pcomm">www-3.ibm.com/software/network/pcomm</a>
NetManage	Rumba	<a href="http://www.netmanage.com/products/rumba/index.asp">www.netmanage.com/products/rumba/index.asp</a>
Tom Brennan Software	Vista tn3270	<a href="http://www.tombrennansoftware.com">www.tombrennansoftware.com</a>
WRQ	Reflection	<a href="http://www.wrq.com/products/reflection">www.wrq.com/products/reflection</a>

**Figure 3** Commercial Workstation Software

At this point you will need to use your file transfer feature to "upload" (i.e. send) the *xdcxmit.trs* file from your PC to your mainframe. When you perform the upload, please follow these guidelines:

- You must perform a "binary format" file transfer. This means that the transfer process **must not** attempt to translate the file from ASCII to EBCDIC, and it **must not** attempt to interpret CRLF ("carriage return, line feed") sequences as end-of-record signals.
- The *xdcxmit.trs* must be uploaded to a mainframe dataset having the following characteristics:  
Suggested dsname: DBCOLE.XDCZ12.INSTALL.XDCXMIT.TERSED  
DCB: DSORG=PS, RECFM=FB, LRECL=1024, BLKSIZE=0  
SPACE: (TRK, (500, 100), RLSE)

## **Step 2: Decompress the XDCXMIT Library**

DBCOLE.XDCZ12.INSTALL.XDCXMIT.TERSED is a compressed copy of z/XDC's "pre-installation" library named DBCOLE.XDCZ12.INSTALL.XDCXMIT. To decompress it, you will have to run IBM's TRSMMAIN program. This program is available on most MVS systems, but if for some reason you don't have it, you can download it for free from the following web site: <http://techsupport.services.ibm.com/390/trsmain.html>

Once you have TRSMMAIN, you can run the JCL shown in [Figure 4](#) on page [4](#) in order to decompress DBCOLE.XDCZ12.INSTALL.XDCXMIT.TERSED. A copy of this JCL is available in the distribution package's *product* folder, in a file named *\$unterse.jcl*.

# ***z/XDC® z1.2 INSTALLATION GUIDE***

**(The z/XDC Product Distribution Package)**

```
//$UNTERSE JOB (CSW,UPS), '540-456-8536', CLASS=A, MSGCLASS=A,
//          MSGLEVEL=(1,1), NOTIFY=R9999, TIME=1439
//*
//*****
//*
//* This JCL can be used to decompress z/XDC's XDCXMIT library. *
//*
//*****
//* First, insure that the output library is purged. *
//*****
//*
//RESET EXEC PGM=IEFBR14
//XDCXMIT DD DSN=DBCOLE.XDCZ12.INSTALL.XDCXMIT,
//          UNIT=DISK, SPACE=(TRK,0), DISP=(MOD,DELETE)
//*
//*
//*
//*****
//* Now, build the z/XDC pre-installation library. *
//*****
//*
//UNTERSE EXEC PGM=TRSMAN, PARM=UNPACK, REGION=0M
//SYSPRINT DD SYSOUT=*
//INFILE DD DSN=DBCOLE.XDCZ12.INSTALL.XDCXMIT.TERSED, DISP=SHR
//OUTFILE DD DSN=DBCOLE.XDCZ12.INSTALL.XDCXMIT,
//          UNIT=SYSALLDA, DISP=(,CATLG),
//          SPACE=(TRK,(1400,500,5),RLSE),
//          DCB=(RECFM=FB,LRECL=80,BLKSIZE=0)
```

**Figure 4** Sample JCL for Decompressing DBCOLE.XDCZ12.INSTALL.XDCXMIT

### **Step 3: Extract the Installation Libraries from DBCOLE.XDCZ12.INSTALL.XDCXMIT**

DBCOLE.XDCZ12.INSTALL.XDCXMIT is a partitioned dataset whose members are xmit files (i.e. files created by TSO's XMIT command). These members need to be processed by the TSO's RECEIVE<sup>1</sup> command to produce the z/XDC installation libraries. Information about these libraries is shown in [Figure 5](#) on page [5](#).

# ***z/XDC® z1.2 INSTALLATION GUIDE***

(The z/XDC Product Distribution Package)

<b>The Pre-Installation Library</b> (DBCOLE.XDCZ12.INSTALL.XDCXMIT)		
<b>This Member ...</b>	<b>... Produces this Installation Library</b>	
XDCADATA	DBCOLE.XDCZ12.INSTALL.XDCADATA	
XDCJCL	DBCOLE.XDCZ12.INSTALL.XDCJCL	
XDCLOAD	DBCOLE.XDCZ12.INSTALL.XDCLOAD	
XDCTEXT	DBCOLE.XDCZ12.INSTALL.XDCTEXT	
<b>This Installation Library ...</b>	<b>... Has These Characteristics</b>	
DBCOLE. --- .XDCADATA	SPACE= (TRK, (1400, 500, 5))	DCB= (RECFM=VB, LRECL=8188)
DBCOLE. --- .XDCJCL	SPACE= (TRK, (20, 10, 5))	DCB= (RECFM=FB, LRECL=80)
DBCOLE. --- .XDCLOAD	SPACE= (TRK, (300, 100, 10))	DCB= (RECFM=U, BLKSIZE=6144)
DBCOLE. --- .XDCTEXT	SPACE= (TRK, (10, 50, 50))	DCB= (RECFM=FB, LRECL=80)
<b>Other Members of the Pre-Installation Library</b>		
<b>Member</b>	<b>Purpose</b>	
\$README	Contains a summary of the installation process.	
\$RECEIVE	Contains JCL for extracting the above installation libraries from the pre-installation library.	

**Figure 5** z/XDC Installation Libraries

To extract the installation libraries, run the JCL found in DBCOLE.XDCZ12.INSTALL.XDCXMIT(\$RECEIVE). This job uses TSO's RECEIVE<sup>1</sup> commands (not SMP/E's RECEIVE command) to (re)build the four installation libraries shown in [Figure 5](#) on page [5](#).

Note, the z/XDC installation process assumes that all z/XDC related datasets have names that start with "DBCOLE.XDCZ12.". You may change them to something else later (see "*Choose Naming Conventions ...*" on page [10](#) for more information about this); however for now, life for the both of us will be somewhat easier if you leave the datasets named as they are.

You are now ready to proceed with installing z/XDC.

# ***z/XDC® z1.2 INSTALLATION GUIDE***

**(The z/XDC Product Distribution Package)**

# *z/XDC® z1.2 INSTALLATION GUIDE*

## INSTALLING THE EXTENDED DEBUGGING CONTROLLER

The installation process for z/XDC uses SMP/E<sup>6</sup>. There are essentially three phases to the installation process: The pre-SMP/E Phase, the SMP/E Phase, and the post-SMP/E Phase.

- In the pre-SMP/E Phase, installation datasets for z/XDC are created. These consist of the target datasets, the DLIB datasets, and the SMP datasets themselves. In addition, current maintenance for z/XDC has to be downloaded from our web site ([www.colesoft.com](http://www.colesoft.com)).
- In the SMP/E Phase, SMP/E is executed to RECEIVE, APPLY, and ACCEPT the base z/XDC product into the z/XDC target and DLIB datasets. Also, current maintenance is RECEIVE'd and APPLY'd (but not ACCEPT'd) into the z/XDC target datasets.
- In the post-SMP/E Phase, a variety of tasks are performed in order to copy z/XDC elements from your target libraries to your production libraries, to activate z/XDC, and to make its various features available to your user community.

## **z/XDC z1.2's Compatibility with XDC's Prior Versions/Releases (XDC X3.3 and XDC/SE S2.0)**

In general, multiple versions and releases of z/XDC can coexist on the same system. If you need to run this release of z/XDC concurrently with a prior version or release, review the following:

- **Installation Datasets:** For the SMP/E Phase of the installation process, you should create new SMP/E libraries and new DLIB and target z/XDC datasets that are separate from those used by prior versions and releases. (See "*Choose Naming Conventions ...*" on page [10](#).)
- **Load Module Names:** z/XDC load module names generally have not changed; therefore:
  - Two versions or releases of z/XDC libraries cannot effectively coexist in your linklist and LPA-list concatenations. Accordingly, during a "try-out" period, z/XDC's load modules need not be installed into your linklist and LPA-list. Instead, they can be invoked via //JOB LIB, //STEPLIB, and equivalent techniques. (See "*Adding XDCPLPA*" on page [18](#) and "*Adding XDCLINK*" on page [18](#).)
  - Alternatively, all of z/XDC's load modules can be renamed. As distributed, all of z/XDC's load module names start with the characters "XDC". You can rename these modules to any other 3-character string (such as "z12"). If you do so, then multiple levels of z/XDC can exist in your linklist and LPA-list libraries; however, user programs that locate z/XDC by name may have to be reassembled. See "*Renaming z/XDC*" on page [15](#) for more information.
- **z/XDC's Service and Hook SVCs:** z/XDC internally installs and manages two SVC routines and several system intercepts. It does this in such a way that any two or more versions and releases of the SVCs can automatically coexist and not interfere with each other (regardless of whether or not XDC has been renamed). See "*Installing z/XDC's Service and Hook SVCs*" on page [38](#) for more information.
- **Clists and ISPF Elements:** [Figure 12](#) on page [23](#) shows the old and new names of the various elements of z/XDC relating to ISPF. As you can see, the names of some of these elements have changed while others have not. Those elements whose names have changed can, of course, coexist with their older counterparts. Those elements whose names have not changed are backwards compatible with the older versions and releases of z/XDC. Accordingly, when installing the new z/XDC, you can replace the old clists and ISPF elements with the new ones. In fact you should perform these replacements because the older elements are not always forward compatible with the newer z/XDC.

---

<sup>6</sup>**Now don't panic!** I myself am an SMP-phobe from way back! I feel your pain (-). Trust me, I've put a lot of effort into making this as painless a process as possible. If you don't like SMP, if you don't know SMP, if you don't want to know SMP, then this is the installation process for you. It is self contained, and it works very well. Just use the installation jobs and process that I've supplied, and you won't have to go anywhere near your system's SMP libraries. In fact, you will have an easier time than the experienced Sysprog who is probably going to insist on remangling this stuff into something that works "the right way". (Oh well.)

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Installing the Extended Debugging Controller)**

- **The Cross Domain Facility (CDF):** CDF can be executed simultaneously with other copies of CDF from prior versions and releases of z/XDC, even when the prior CDF is using a z/XDC that has not been renamed. In addition, multiple copies of CDF from the same release can be executed just so long as they are using z/XDC's having different names. (See "*Renaming z/XDC*" on page [15](#) for more information.) Each CDF, however, must be assigned to a unique VTAM node containing a uniquely named set of APPLID's. See "*Installing z/XDC's Cross Domain Facility (CDF)*" on page [49](#) for more information.

## **Installation Summary**

The following is a summary of the required and optional steps for installing z/XDC.

### **Pre-SMP/E Phase:**

- 1.) Choose a naming convention for z/XDC's datasets. (page [10](#))
- 2.) Download from our web site ([www.colesoft.com](http://www.colesoft.com)) current maintenance for z/XDC. (page [10](#))
- 3.) Upload from your hard drive to your mainframe the maintenance that you downloaded. (page [11](#))
- 4.) DBCOLE.XDCZ12.INSTALL.XDCJCL contains four jobs: SMPCSI, SMPDDEF, SMPBASE, and SMPMAINT. Edit these jobs to meet local jobcard, dataset naming, and other requirements. (page [11](#))
- 5.) Run the SMPCSI job (from DBCOLE.XDCZ12.INSTALL.XDCJCL) to create a CSI database and other SMP datasets for z/XDC. (page [12](#))
- 6.) Run the SMPDDEF job (from DBCOLE.XDCZ12.INSTALL.XDCJCL) to create DDDEFs in z/XDC's CSI database for z/XDC's target and DLIB datasets. (page [12](#))

### **SMP/E Phase:**

- 1.) Run the SMPBASE job (from DBCOLE.XDCZ12.INSTALL.XDCJCL) to RECEIVE, APPLY, and ACCEPT the z/XDC base product into the z/XDC target and DLIB datasets. (page [14](#))
- 2.) Run the SMPMAINT job (from DBCOLE.XDCZ12.INSTALL.XDCJCL) to RECEIVE and APPLY current maintenance. **This step is REQUIRED! z/XDC will refuse to come up until maintenance has been APPLY'd!** (page [14](#))

### **Post-SMP/E Phase:**

- 1.) All z/XDC related load modules have names starting with the characters "XDC". You may, at this point, want to rename z/XDC to some other 3-character name of your choice. (page [15](#))
- 2.) The z/XDC target libraries can now be copied to or concatenated to various system libraries. (page [17](#))
- 3.) You may have to re-IPL your system, possibly with a CLPA. (page [26](#))
- 4.) Licensing: Run z/XDC from a TSO session. The first time you do this, z/XDC automatically invokes a "License Definition" panel. You must fill in the required information in order to activate z/XDC for your system. (page [26](#))
- 5.) If your site uses a security system (RACF, CA-ACF2, or CA-Top Secret), then rules must be defined in

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Installing the Extended Debugging Controller)**

that system to permit selected users to run z/XDC in various authorized modes. (page [29](#))

- 6.) An "XDCINIT" job needs to be setup to run at system IPL time to dynamically install a couple of SVCs that z/XDC needs for performing certain of its functions. z/XDC's SVCs must be dynamically reinstalled at every IPL. (page [38](#))
- 7.) Perform an Installation Verification Test to verify that the installation of z/XDC to this point is correct. (page [40](#))
- 8.) Set up the `DBCOLE.XDCZ12.XDCADATA` library as a default MAPLIB<sup>7</sup> library for all z/XDC users. (page [43](#))
- 9.) z/XDC has a large number of user and installation settable profile options. You need to review the various default settings, make any changes you deem appropriate, and save the changed settings as a new default profile for other z/XDC users on your system. (page [44](#))
- 10.) Install the necessary PROCs, VTAM definitions, and system commands to enable use of z/XDC's Cross Domain Facility ("CDF") for debugging background jobs and system tasks. (page [49](#))
- 11.) The Installation Verification Test should now be repeated using CDF to verify that the facility is installed correctly. (page [52](#))
- 12.) z/XDC supports an installation exit ("security interface replacement") and several user exits. The user exits are "front/back end", "initialization", "termination", "resumption", "user-SVC", "user communications interface", and "user defined commands". Eventually, users may want to code one or more of these exit routines. Existing exits will have to be reassembled. (page [53](#))
- 13.) The XDCJES2 library contains an interface to z/XDC for debugging local mods to JES2. You may want to install this interface. (page [56](#))

Expanded discussions of the above outlined installation steps follow.

## **Pre-SMP/E Installation Phase**

The installation process for z/XDC has been designed to use its own private target, DLIB, and SMP datasets, including its own private CSI ("Consolidated Software Inventory", a VSAM database for SMP/E). There are several reasons for this:

- The z/XDC product has no complex dependencies on the release and maintenance levels of other products or of z/OS itself. (z/XDC runs on all versions of z/OS and OS/390.) Accordingly, there is no need for it to be installed in the same target or DLIB zone as any other product or system.
- The SMP/E zone, options, and utilities definitions that work best for z/XDC's installation process may not be compatible with the definitions found within existing CSI databases for z/OS or other products.
- The z/XDC distribution contains several hundred macros and other elements, and Cole Software cannot guarantee that the names of these elements are unique among all products.
- The private SMP datasets are small and pose no significant impact against free disk space.
- The use of private datasets permits a uniform and simplified installation process for all our customers and, therefore, simplifies our task of providing as automated an installation and maintenance process as possible.

---

<sup>7</sup>A **MAPLIB** library is a library that contains ADATA files created by an assembler and from which z/XDC's MAP and DMAP commands can build Source Image Maps for use in Source Level Debugging.

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Installing the Extended Debugging Controller)**

- The creation of the SMP datasets and the basic installation of the z/XDC product can be done with just four standard jobs requiring only minimal customization for local needs. **This permits even those programmers having little or no understanding of SMP/E to install z/XDC successfully.**
- Use of private datasets makes it possible for individual user groups (where appropriate) to install their own private copies of the z/XDC product **and not have to involve unnecessarily a centralized Systems Programming staff** (except for certain elements of the Post-SMP/E Installation Phase).
- If severe problems occur during the SMP/E Phase, the current installation process can be abandoned and restarted simply by rerunning the four installation jobs (which will automatically delete and reallocate the SMP, DLIB, and target datasets).

### **Step 1: Choose Naming Conventions for z/XDC's Target, DLIB, and SMP Datasets**

The dataset names for z/XDC's SMP libraries and for z/XDC's target and DLIB datasets all should include your favorite hi-level qualifier, the product name ("XDC"), and z/XDC's current release ("z12"). This will allow you to install separate releases of z/XDC into separate libraries, which is useful if you want to "try out" a new release before committing to it. In this Guide, I will use "DBCOLE.XDCZ12." as the naming convention for the z/XDC datasets.

If you plan to add z/XDC's load libraries to your system's linklist and LPA-list concatenations (see "*Adding z/XDC's Target Libraries to Your System*" on page 17), then you should consider the pros and cons of choosing a hi-level qualifier that catalogs to your system's Master Catalog. Considerations:

- If the z/XDC datasets **are** cataloged in the Master Catalog, then the volser names of the DBCOLE.XDCZ12.XDCLINK and DBCOLE.XDCZ12.XDCPLPA libraries do not have to be specified in the LINKLIST, LPA-list, and APF sections of the active PROGxx member of SYS1.PARMLIB.
  - **Advantage:** The datasets can be moved without requiring that SYS1.PARMLIB be updated.
  - **Disadvantage:** Because of issues that occur when upgrading from one release of z/OS to another, it is preferable that the Master Catalog have as few entries as possible.

### **Step 2: Downloading Maintenance from our Web Site**

Maintenance for release z1.2 of z/XDC is distributed in a cumulative maintenance file. Every distribution of z/XDC maintenance always contains all applicable maintenance that has been written from the time that z1.2 was released until the time that the maintenance file was created. Therefore, whenever you obtain a new maintenance file, you can always discard any older files that you may have previously obtained, regardless of whether or not you ever got around to APPLY'ing the older files.

z/XDC maintenance is provided in SMP/E format and in most cases is APPLY'd to z/XDC using the SMPMAINT job. See "*Step 2: Run the SMPMAINT Job*" on page 14 for details.

z/XDC maintenance is distributed from our Internet web site. Start at [www.colesoft.com](http://www.colesoft.com), and navigate as follows:

- From our home page, click on **Maintenance**. This will take you to our maintenance page.
- Read carefully and completely the entirety of the maintenance page. This is where last minute maintenance instructions and processing information is published. This is the only place where this information is published.
- Click on the "Contents and Dates" oval, and read the information therein. This is where instructions specific to the particular maintenance file are published. This is the only place where this information is published.
- Finally, select the appropriate file download oval, and click on it in the manner instructed on the page.

The file named *z12maint.ebc* will then be downloaded to your hard drive.

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Installing the Extended Debugging Controller)**

So, right now, please go to our web site and download current maintenance.

!!!!!!  
**PLEASE DO NOT CONTINUE THE z/XDC INSTALLATION PROCESS UNTIL THE  
MAINTENANCE HAS BEEN DOWNLOADED**  
!!!!!!

Otherwise, you will just have to repeat many of the installation steps later.

If you need any assistance whatsoever with downloading the maintenance, then please feel free to call us immediately. On the other hand, *please do not try to use, test, or in any way run z/XDC without its maintenance applied*. Doing so will just lead to unnecessary tech support calls that do nothing more than waste both your time and mine.

### **Step 3: Upload the Maintenance to Your Mainframe**

Once you have downloaded the current *z12maint.ebc* maintenance file from our web site, you will then need to upload it to your mainframe. The file is encoded in a mixture of mainframe EBCDIC and binary. Therefore, it needs to be uploaded to the mainframe as a **binary** file.

Upload *z12maint.ebc* to a sequential dataset named `DBCOLE.XDCZ12.XDCMAINT` (depending upon the z/XDC dataset naming conventions that you have chosen). The DCB attributes of that dataset need to be `RECFM=FB`, `LRECL=80`, and `BLKSIZE=n*80` (e.g. `BLKSIZE=27920`).

The upload procedure differs depending upon the particular workstation software in use on your PC, so you will have to refer to your workstation documentation for specific information. The following requirements need to be met.

- The upload procedure must not attempt to perform any ASCII-to-EBCDIC translation! So, depending upon the particular PC workstation program that you use, you will have to specify one of the following for the transfer:
  - TRANSLATION OFF
  - CONVERSION OFF
  - TRANSPARENCY ON
  - BINARY TRANSFER
- The upload procedure must not attempt to removed CR/LF's ("carriage returns" and "linefeeds") from *z12maint.ebc*. Generally, CR/LF's exist only for ASCII-encoded text files, which *z12maint.ebc* is not. Some workstation programs may refer to the CR/LF's as "line ends".

Now that you've uploaded the maintenance to your mainframe, you're ready to continue with the installation process. Don't apply the maintenance yet though, that's still a few steps down the road.

### **Step 4: Edit the DBCOLE.XDCZ12.INSTALL.XDCJCL Jobs According to Local Requirements**

"The *z/XDC Product Distribution Package*" on page [1](#) explained how to load the `DBCOLE.XDCZ12.INSTALL.XDCJCL` library to your mainframe from the Distribution Package. The `DBCOLE.XDCZ12.INSTALL.XDCJCL` library contains four jobs that should be used for installing z/XDC onto your system. These jobs are:

- **SMPCSI** creates SMP datasets (including a CSI) for z/XDC's private use. If one or more of the datasets already exist, then they are deleted and recreated. **SMPCSI** also initializes the CSI with appropriate zone definitions, options and utility entries, and DDDEFs for the other SMP datasets created.
- **SMPDDDEF** adds DDDEFs to the CSI for z/XDC's target and DLIB datasets. It also creates (or recreates)

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Installing the Extended Debugging Controller)**

the target and DLIB datasets themselves.

- **SMPBASE** RECEIVE's, APPLY's, and ACCEPT's the z/XDC base product.
- **SMPMAINT** first RESTORE's and REJECT's old maintenance from the z/XDC target libraries. It then RECEIVE's and APPLY's new maintenance to the target libraries. This job should be used whenever you need to apply maintenance to z/XDC.

You may want to print listings of the four jobs for review. The jobs each contain helpful commentary that you should read. In particular, the commentaries describe the specific editing changes that you will have to make in order to customize the jobs to meet your local requirements.

### **Step 5: Run SMPCSI to Create SMP Datasets for z/XDC**

SMPCSI creates SMP datasets (including a CSI database) for z/XDC's private use. ([Figure 6](#) on page [12](#) shows the datasets created.) If one or more of the datasets already exist, then they are deleted and recreated. SMPCSI also initializes the CSI database with appropriate zone definitions, options and utility entries, and DDDEFs for the other SMP datasets created.

<b>DSNAME</b>	<b>Type</b>	<b>Comment</b>
DBCOLE.XDCZ12.CSI	VSAM	SMP/E's "Consolidated Software Inventory" database.
DBCOLE.XDCZ12.SMPLOG	Sequential	SMP/E's activity log.
DBCOLE.XDCZ12.SMPMTS	Partitioned	Temporary target level macro library.
DBCOLE.XDCZ12.SMPPTS	Partitioned	Temporary sysmod storage library.
DBCOLE.XDCZ12.SMPSCDS	Partitioned	Temporary backup storage library for target zone entries changed by JCLIN data during APPLY processing.
DBCOLE.XDCZ12.SMPSTS	Partitioned	Temporary target level source module library.

**Figure 6** The SMP/E Datasets Created by the SMPCSI Job

Note that if you have previously started the z/XDC installation process and you now wish to abandon that work and start over, you can do so simply by rerunning this SMPCSI job and the SMPDDDEF job (see below). These two jobs will delete and reallocate all of z/XDC's target, DLIB, and SMP datasets.

Read the commentary within the sample SMPCSI job for more information about required editing changes and expected completion codes.

### **Step 6: Run SMPDDDEF to Create z/XDC Target and DLIB Datasets**

SMPDDDEF adds DDDEFs to the CSI database for z/XDC's target and DLIB datasets. It also creates the target and DLIB datasets themselves. ([Figure 7](#) on page [13](#) shows the datasets created.) If one or more of the datasets already exist, then they are deleted and recreated.

This job should be executed after the SMPCSI job. Read the commentary within the sample SMPDDDEF job for more information about required editing changes and expected completion codes.

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Installing the Extended Debugging Controller)**

<b>DSNAME</b>	<b>Level</b>	<b>Comment</b>
DBCOLE.XDCZ12.XDCDLIB.XDCDLINK	DLIB	All z/XDC load modules.
DBCOLE.XDCZ12.XDCDLIB.XDCDTEXT	DLIB	All other z/XDC elements (Selected source, macros, panels, tables, parm files, etc.)
DBCOLE.XDCZ12.XDCADATA	DLIB	ADATA files including source image information for a large number of IBM system control blocks.
DBCOLE.XDCZ12.XDCLINK	Target	z/XDC load modules for installation into a linklist library.
DBCOLE.XDCZ12.XDCPLPA	Target	z/XDC load modules for installation into the PLPA.
DBCOLE.XDCZ12.XDCCMDS	Target	z/XDC command files for end-user use via z/XDC's "READ" command.
DBCOLE.XDCZ12.XDCCDF	Target	A parameter file, VTAMLST data, and a sample PROC for running z/XDC's Cross Domain Facility.
DBCOLE.XDCZ12.XDCMLIB	Target	ISPF message modules.
DBCOLE.XDCZ12.XDCPLIB	Target	ISPF panels.
DBCOLE.XDCZ12.XDCTLIB	Target	ISPF table modules.
DBCOLE.XDCZ12.XDCCLIST	Target	Clists used for running z/XDC under ISPF.
DBCOLE.XDCZ12.XDCSAMP	Target	Sample ACF2 security definitions. Sample terminal LOGMODE tables.
DBCOLE.XDCZ12.XDCJES2	Target	Source code, an update file, and misc. JCL for installing a debugging interface into JES2.
DBCOLE.XDCZ12.XDCASM	Target	Selected z/XDC sample source modules.
DBCOLE.XDCZ12.XDCMACS	Target	Assembler macros needed for assembling the modules in XDCASM.
DBCOLE.XDCZ12.XDCJCL	Target	Sample jobs for assembling the distributed source modules and for relinkedediting the distributed load modules.
DBCOLE.XDCZ12.XDCOBJ	n/a	An object file library for use when manually assembling the sample source modules in DBCOLE.XDCZ12.XDCASM.

Note: DLIB libraries will never have z/XDC maintenance applied. Only target level libraries will be updated by z/XDC maintenance.

**Figure 7** The Target and DLIB Datasets Created by the SMPDDEF Job

### **SMP/E Installation Phase**

This phase of z/XDC's installation procedure uses SMP/E to copy z/XDC elements into 13 target libraries and 3 DLIB libraries<sup>8</sup> ([Figure 7](#) on page [13](#)). It also applies all current maintenance to z/XDC.

<sup>8</sup>"DLIB" is short for "distribution library" but that name does not accurately indicate what a DLIB library really is. These days, "DLIB libraries" are a set of libraries used by SMP/E as backups for target libraries (also sometimes called "TLIBs"). If bad program elements are installed onto target libraries, then theoretically they can be removed by copying corresponding elements from the DLIBs back to the target libraries. (This copying would be done by SMP/E's "RESTORE" command.)

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Installing the Extended Debugging Controller)**

### **Step 1: Run the SMPBASE Job**

The SMPBASE job RECEIVE's the z/XDC base product into SMP/E, APPLY's it to z/XDC's 13 target libraries, and ACCEPT's it into the 3 DLIB libraries.

The SMPBASE job can be executed directly after running the SMPDDEF job. Read the commentary within the sample SMPBASE job for more information about required editing changes and expected completion codes.

In particular, please note that during the APPLY step, several warning messages will be issued by SMP/E. They are "GIM44402W SRCxxxxx WAS NOT ASSEMBLED ...". These messages can be ignored. They are for several source modules that are distributed only as samples.

### **Step 2: Run the SMPMAINT Job**

**APPLY'ing current maintenance is a REQUIRED step. z/XDC will refuse to come up until maintenance has been APPLY'd!**

The SMPMAINT job must be executed to apply maintenance to z/XDC whenever you install z/XDC and again whenever you obtain a new maintenance file (*z12maint.ebc*). This can be obtained only via a download from our Internet web site ([www.colesoft.com](http://www.colesoft.com)). See *Step 2: Downloading Maintenance from our Web Site* on page [10](#) for more information.

If you have accumulated more than one *z12maint.ebc* maintenance file, always apply only the file having the latest date. All older files can be discarded. This is because z/XDC maintenance is always cumulative: Every maintenance file always contains all the maintenance necessary to bring z/XDC all the way from its distribution level up to the level that was current at the time that we built that file. In other words, every maintenance file always includes all of the maintenance previously included in all older files.

If you've obtained a maintenance file, then you should already have uploaded it to your mainframe (*Step 3: Upload Additional Maintenance to Your Mainframe* on page [11](#)). So now you must run the SMPMAINT job at this time in order to apply that maintenance to z/XDC.

The SMPMAINT job first uses SMP/E to RESTORE and REJECT all maintenance (including initial maintenance) that may have been previously APPLY'd. (SMP/E does this, of course, by copying product elements from the DLIB datasets to appropriate target level datasets. This is why it is important that z/XDC maintenance never be ACCEPT'd into the DLIB datasets.) SMPMAINT then RECEIVE's and APPLY's the new maintenance onto the target level datasets.

During initial product installation, the SMPMAINT job must be executed directly after running the SMPBASE job. During subsequent maintenance processing, SMPMAINT can be executed by itself without the other three jobs.

Read the commentary within the sample SMPMAINT job for more information about required editing changes and expected completion codes.

*Do not attempt to perform APPLY CHECK!*

Normally, APPLY CHECK would be a sensible thing to do when APPLY'ing maintenance, and in the more typical case where products follow an incremental philosophy for their maintenance, this would work just fine. But it is not ever expected to work for our z/XDC product, and it should never be attempted.

This is because z/XDC maintenance is cumulative, not incremental. This means that each maintenance file that we develop contains all maintenance for the product, not just new maintenance. Consequently, before applying a new maintenance file, all old maintenance must first be removed.

So it follows that the maintenance files that we create are structured to APPLY successfully to a completely virgin, base copy of the product. They will not APPLY successfully to a copy of the product that already has older

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Installing the Extended Debugging Controller)**

maintenance applied. Consequently, the **required** SMP/E command sequence must be a RESTORE followed by a REJECT followed by a RECEIVE followed by an APPLY. (This is what the SMPMAINT job does.)

If you try to run an APPLY CHECK, it will occur against a copy of the product for which RESTORE has not yet been done. In other words, the APPLY CHECK will be done against a level of the product for which the maintenance was not written. Consequently, it will always<sup>9</sup> fail. Bottom line:

- APPLY CHECK is not ever expected to be successful. Don't even try it.
- APPLY REDO is never expected to be successful. Don't even try it.
- ACCEPT MUST NEVER BE DONE!

## **Post-SMP/E Installation Phase**

So much for the easy part! There still remains several tasks that need to be performed in order to complete the z/XDC installation process.

### **Step 1: Renaming z/XDC**

You may, if you wish, rename z/XDC to any other 3-character name you choose. The names of all z/XDC load modules in DBCOLE.XDCZ12.XDCLINK and in DBCOLE.XDCZ12.XDCPLPA start with the characters "XDC". These first three characters can be changed to Z12, to DBC, to your initials, or to any other legal three characters you choose. The remaining characters in each name must not be altered.

A renamed z/XDC is referred to as a z/XDC "clone".

Before deciding to rename z/XDC, consider the following:

- If you change the names of any z/XDC load modules, then you must change the names of all of them.
- The z/XDC modules should not be renamed directly within the DBCOLE.XDCZ12.XDCLINK and DBCOLE.XDCZ12.XDCPLPA libraries. Instead, you must first copy the modules to other libraries and then rename them there.
- You will have to repeat this process each time that you apply z/XDC maintenance.
- If user programs are written to invoke z/XDC internally, then they will become dependent upon the name that you choose. Thus, your name choice will become "locked in" over time.
- Renaming z/XDC will permit you to let two or more releases of z/XDC coexist in your linklist and LPA-list libraries. However, renaming z/XDC is not always necessary for permitting multiple versions or releases to coexist on your system (see "*z/XDC z1.2's Compatibility with XDC's Prior Versions/Releases (XDC X3.3 and XDC/SE S2.0)*" on page 7).

If you do decide to rename z/XDC, then first use IEBCOPY to copy the z/XDC load modules to a new library. (See [Figure 8](#) on page 16.) Note that IEBCOPY is the only copying program that you can use to do this successfully. This is because one of z/XDC's load modules (XDCHLPM) is an overlay structured module and so cannot be copied by most other means. Specifically, XDCHLPM cannot be copied either by ISPF's "Move/Copy Utility" (option 3.3) or by IBM's "Bulk Data Transfer" utility (BDT).

---

<sup>9</sup>Actually, APPLY CHECK could succeed prior to the very first time you APPLY maintenance, but after that, it will always fail.

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Installing the Extended Debugging Controller)**

```
//      --- JOB ---
//COPY   EXEC  PGM=IEBCOPY
//SYSPRINT DD  SYSOUT=*
//IN1    DD   DSN=DBCOLE.XDCZ12.XDCLINK,DISP=SHR
//IN2    DD   DSN=DBCOLE.XDCZ12.XDCPLPA,DISP=SHR
//OUT    DD   DSN=DBCOLE.XDCZ12.XDCLINK.USER,DISP=(,CATLG),
//        UNIT=DISK,SPACE=(TRK,(250,50,20),RLSE),DCB=* .IN1
C I=(IN1,IN2),O=OUT
```

**Figure 8** Model JCL for Copying z/XDC Load Modules Prior to Renaming Them

After you have copied the z/XDC load modules to a new library, you can then rename them. Unfortunately however, even this can be challenging. This is because one of the load modules, XDCCALL, has three alias names: XDCCMD, XDCCALLA, and XDCCMDA. The directory entry for each of these aliases identifies XDCCALL as the module's primary name, and IBM provided tools (such as ISPF's "Library Utility", option 3.1) do **not** offer any mechanism for updating alias directory entries when renaming a primary name. There is, however, a popular "shareware" TSO command named PDS<sup>10</sup> which will automatically perform the necessary updating when used to rename primary names.

In the absence of the PDS<sup>10</sup> command, in order to rename XDCCALL and its aliases, you will have to relinkedit the module and assign the new names that way. The basic JCL for doing this is available in DBCOLE.XDCZ12.XDCJCL(LCALL) and is shown below in [Figure 9](#) on page 16. This process creates two new copies of the XDCCALL load module: one named xxxCALLA (with an alias of xxxCMDA) for authorized debugging and one named xxxCALL (alias is xxxCMD) for non-authorized debugging.

```
//LCALL   JOB (COLE,UPS,,999,,),'540-456-8536',NOTIFY=R9999,
//        MSGLEVEL=(1,1),MSGCLASS=T,PRTY=12,TIME=60
//*
//LCALL   EXEC  PGM=IEWL,REGION=0M,
//        PARM=(XREF,MAP,LIST,LET,RENT,REUS,REFR,NCAL)
//SYSPRINT DD  SYSOUT=*
//SYSUT1  DD   UNIT=SYSDA,SPACE=(CYL,(1,1))
//SYSLMOD DD   DSN=DBCOLE.XDCZ12.XDCLINK.USER,DISP=SHR
//XDCLINK DD   DSN=DBCOLE.XDCZ12.XDCLINK,DISP=SHR
//SYSLIN  DD   *
INCLUDE  XDCLINK(XDCCALL)
ENTRY   XDCCALL
SETCODE AC(1)
MODE    AMODE(31),RMODE(24)
ALIAS   XDCCMDA
NAME    XDCCALLA(R)
INCLUDE XDCLINK(XDCCALL)
ENTRY   XDCCALL
MODE    AMODE(31),RMODE(24)
ALIAS   XDCCMD
NAME    XDCCALL(R)
```

This JCL assumes that DBCOLE.XDCZ12.XDCLINK.USER is the target library for the renamed copy of z/XDC. The model for this JCL is available in DBCOLE.XDCZ12.XDCJCL(LCALL).

**Figure 9** Model JCL for Renaming XDCCALL via Relinkedit

<sup>10</sup>PDS is a "shareware" command found on the "CBT" mods tape, currently (December 3, 2003) available for a nominal fee from [www.cbttape.org](http://www.cbttape.org). Also, a vendor supported successor product named "STAR TOOLS" can be purchased from [Serena](http://www.serena.com): 800-457-3736. WEB: [www.serena.com](http://www.serena.com), then select "products", then "Star Tools".

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Installing the Extended Debugging Controller)**

The remainder of this **Install Guide** assumes that z/XDC has not been renamed.

### **Step 2: Adding z/XDC's Target Libraries to Your System**

z/XDC's various target libraries are shown in [Figure 7](#) on page 13. Of these, the following need to be "added" to your system libraries: XDCLINK, XDCPLPA, XDCMLIB, XDCPLIB, XDCTLIB, XDCCLIST, and XDCCMDS. By "added" I mean that these libraries need to be either copied into or concatenated to your corresponding system libraries. The choice depends upon your local installation standards.

z/XDC's load modules are contained in the DBCOLE.XDCZ12.XDCLINK and DBCOLE.XDCZ12.XDCPLPA libraries. [Figure 10](#) on page 17 lists the individual load modules, what their functions are, and where they should go on your system. More specific information follows.

<b>Module</b>	<b>System Library</b>	<b>Authorization Needed?</b>	<b>Function</b>
XDC	an LPA-list library*	No	Is the Extended Debugging Controller. Must reside in 24-bit storage.
XDC31	an LPA-list library*	No	Is the portion of z/XDC that can reside in 31-bit storage.
XDCTFS	a linklist library	Yes	Provides Fullscreen Support and Cross Domain Facilities (CDF) for z/XDC.
XDCCALL	a linklist library	No	Is used to debug programs under TSO or in the batch.
XDCCALLA	a linklist library	Yes	Is used to debug authorized programs under TSO or in the batch. This is actually an alias for XDCCALL.
XDCCMD	a linklist library	No	Is used to debug commands under TSO. This is actually an alias for XDCCALL.
XDCCMDA	a linklist library	Yes	Is used to debug authorized commands under TSO. This is actually an alias for XDCCALL.
XDCXITS	a linklist library	No	A sample user exit module that implements a "LIST TIOT" command. (See SRCXUCMD and SRCXITSR.)
XDCHELPM	a linklist library	No	Contains frames for z/XDC's Online HELP command.
XDCMAPS	a linklist library	No	Contains z/OS control block maps for use by the "DMAP" command.
XDCSYMED	a linklist library	No	Is an object deck SYM table editor.
XDCLCNSE	a linklist library	No	Contains license control data.
XDCIVP	none	No	Is an "Installation Verification Program".
XDCONLHG	none	No	Is a sample program that illustrates how to write a "User Communications Interface" exit for z/XDC.

\*The XDC and XDC31 load modules should be placed in an LPA-list library only if it is anticipated that it will be used either to debug modules located within common storage (i.e, PLPA modules, MLPA modules, etc.) or to debug programs that execute in Cross Memory Mode (e.g. PC routines). If not, then XDC and XDC31 can, instead, be placed into a linklist library.

**Figure 10** z/XDC's Load Modules and Their Appropriate Target System Libraries

The following discussions make several references to adding information to various members of your system's SYS1.PARMLIB library. It is assumed that you have sufficient knowledge of this library to understand the discussion. If not, then please refer to IBM's **Initialization and Tuning Reference** manual<sup>11</sup> for more information, or consult with your systems programmer, as appropriate.

<sup>11</sup>z/OS: SA22-7592. OS/390: SC28-1752. MVS/ESA: GC28-1635.

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Installing the Extended Debugging Controller)**

### *Adding XDCPLPA*

DBCOLE.XDCZ12.XDCPLPA contains load modules XDC and XDC31. "XDC" is z/XDC's primary load module. It must reside in 24-bit storage. "XDC31" contains that part of z/XDC that can reside in 31-bit storage.

These modules may need to be placed into the system's PLPA. You can do so either by copying the modules to an existing PLPA library or by adding DBCOLE.XDCZ12.XDCPLPA's dsname to the LPA library list.

You need to place XDC and XDC31 into the PLPA only if you expect to use z/XDC in the following situations:

- If you expect to debug modules located in common storage. Examples: PLPA, FLPA, or MLPA load modules. System Nucleus routines. SVC routines. Subsystem service routines.
- If you expect to debug modules that are executed by a system initiator. Examples: Certain SMF exits. Certain RACF exits.
- If you expect to debug programs that execute in Cross Memory Mode. Examples: PC routines.

If you do not anticipate that z/XDC will be used in scenarios such as these, then there is no other reason for putting XDC and XDC31 into the PLPA, and so you might as well not do so.

If you do decide to put these modules into the PLPA, then you must put BOTH of them there.

If you already have a prior release of z/XDC installed in your PLPA, and if you need to install this new release for a "try-out" period without disturbing the older release, then you cannot at this time add the new DBCOLE.XDCZ12.XDCPLPA library to your LPA-list. Instead, you will have to make the DBCOLE.XDCZ12.XDCPLPA library available to your users via //JOB LIB or equivalent techniques. See "*Adding XDCLINK*" on page [18](#) for more information.

If you copy the XDC and XDC31 load modules to an existing LPA-list library, then:

- The DBCOLE.XDCZ12.XDCPLPA library's BLKSIZE is small (=6144), so you should not have to reblock its load modules.
- This copying process will have to be repeated every time you apply z/XDC maintenance to the DBCOLE.XDCZ12.XDCPLPA library.

If you add the DBCOLE.XDCZ12.XDCPLPA library to the LPA-list, then:

- Make sure that DBCOLE.XDCZ12.XDCPLPA's dsname is cataloged in your Master Catalog. (See "*Choose Naming Conventions ...*" on page [10](#).)
- Add DBCOLE.XDCZ12.XDCPLPA's dsname to the LPA section of the active PROGxxx member of SYS1.PARMLIB.

If you do add XDC and XDC31 to an existing or new LPA-list library, you can use the SETPROG Operator command to activate the modules immediately. The commands are:

```
SETPROG LPA,ADD,MOD=(XDC,XDC31),DSN=dsname
DISPLAY PROG,LPA,MOD=XDC
DISPLAY PROG,LPA,MOD=XDC31
```

These commands cause the XDC and XDC31 load modules to be loaded into common storage, making them immediately available for use. Then their locations are displayed.

If you decide not to add the DBCOLE.XDCZ12.XDCPLPA modules to the LPA-list, then you can, instead, add it to the linklist or not add it to any list. In these cases, you should install the DBCOLE.XDCZ12.XDCPLPA library in exactly the same way as you intend to install the DBCOLE.XDCZ12.XDCLINK library. For further information, see the following section: "*Adding XDCLINK*".

### *Adding XDCLINK*

DBCOLE.XDCZ12.XDCLINK contains those z/XDC load modules that should be added to the system's linklist libraries. You may either copy them to an existing linklist library or add the DBCOLE.XDCZ12.XDCLINK library to your linklist concatenation. Alternatively, you may leave DBCOLE.XDCZ12.XDCLINK out of the linklist entirely and, therefore, require users to access the z/XDC modules via //JOB LIB or //STEPLIB.

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Installing the Extended Debugging Controller)**

If you already have a prior release of z/XDC installed in your linklist, and if you need to install this new release for a "try-out" period without disturbing the older release, then you cannot at this time add the new DBCOLE.XDCZ12.XDCLINK library to your linklist. Instead, you will have to make the DBCOLE.XDCZ12.XDCLINK library available to your users via //JOB LIB or equivalent techniques.

If you copy the DBCOLE.XDCZ12.XDCLINK modules to an existing linklist library:

- The target linklist library needs to be authorized.
- Perform the copy using IEBCOPY. Neither ISPF's Move/Copy Utility (option 3.3) nor IBM's Bulk Data Transfer utility (BDT) will work for the XDCHLPM load module because neither facility properly supports overlay structured load modules.
- The DBCOLE.XDCZ12.XDCLINK library's BLKSIZE is small (=6144), so you should not have to reblock its load modules. (But you may if you like. Just use IEBCOPY's COPYMOD command with the MAXBLK operand. See [DFSMS/MVS: Utilities](#)<sup>12</sup> for more information.)
- After copying the z/XDC load modules, perform an "LLA REFRESH" to make them usable (assuming the target linklist library did not expand into extra extents).
- The copying process may have caused your target linklist library to expand into extra extents. If this occurred, then you will have to either re-IPL or use the SETPROG Operator command to rebuild the linklist. The following commands should work:  

```
SETPROG LNKLST,DEFINE,NAME=TEMP,COPYFROM=CURRENT,NOCHECK
SETPROG LNKLST,ACTIVATE,NAME=TEMP
DISPLAY PROG,LNKLST,NAME=CURRENT
```
- This copying process will have to be repeated every time you apply z/XDC maintenance to the DBCOLE.XDCZ12.XDCLINK library.

If you add the DBCOLE.XDCZ12.XDCLINK library to the linklist concatenation:

- Add DBCOLE.XDCZ12.XDCLINK's dsname to the LNKLST section of the active PROGxx member of SYS1.PARMLIB.
- Either make sure that DBCOLE.XDCZ12.XDCLINK's dsname is cataloged in your [Master Catalog](#) (See "[Choose Naming Conventions ...](#)" on page [10](#)), or make sure that DBCOLE.XDCZ12.XDCLINK's volser name is explicitly stated in the entry that you add for DBCOLE.XDCZ12.XDCLINK in the LNKLST section of the active PROGxx member of SYS1.PARMLIB.
- The DBCOLE.XDCZ12.XDCLINK library must be made authorized by your choice of the following methods:
  - Specify LNKAUTH=LNKLST in the active IEASYSxx member of SYS1.PARMLIB.
  - Add DBCOLE.XDCZ12.XDCLINK's dsname and location to the APF section of the active PROGxx member of SYS1.PARMLIB.
- Use the "SETPROG APF,---" and "SETPROG LNKLST,---" commands to authorize the DBCOLE.XDCZ12.XDCLINK library and activate the linklist changes. Examples:  

```
SETPROG APF,ADD,DSN=DBCOLE.XDCZ12.XDCLINK,VOL=vvvvvv
SETPROG LNKLST,DEFINE,NAME=TEMP,COPYFROM=CURRENT,NOCHECK
SETPROG LNKLST,ADD,NAME=TEMP,DSN=DBCOLE.XDCZ12.XDCLINK,ATTOP,VOL=vvvvvv
SETPROG LNKLST,ACTIVATE,NAME=TEMP
DISPLAY PROG,LNKLST,NAME=CURRENT
```

These commands are documented in IBM's [z/OS: MVS System Commands](#)<sup>13</sup>.

---

<sup>12</sup>z/OS: SC26-7414. OS/390: SC26-4926.

<sup>13</sup>z/OS: SA22-7627. OS/390: GC28-1781.

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Installing the Extended Debugging Controller)**

If you elect to leave the `DBCOLE.XDCZ12.XDCLINK` library and modules out of the linklist entirely:

- The `DBCOLE.XDCZ12.XDCLINK` library must be made authorized by adding `DBCOLE.XDCZ12.XDCLINK`'s dsname and location (volser) to the APF section of the active `PROGxx` member of `SYS1.PARMLIB`. You will have to issue a "SETPROG APF,---" command to activate the authorization immediately without requiring an IPL.
- Users will have to use `//JOB LIB` or `//STEPLIB` (or equivalents) in order to use `z/XDC`. But be aware that if you want to use `z/XDC` authorized, then the `//JOB LIB` or `//STEPLIB` concatenation must NOT include nonauthorized libraries. (Doing so "poisons" the concatenation, causing all libraries to be treated as being nonauthorized.)
- Also note, if you need to run `z/XDC` authorized under ISPF, then you will NOT be able to use ISPF's LIBDEF facility to access the `DBCOLE.XDCZ12.XDCLINK` and `DBCOLE.XDCZ12.XDCPLPA` libraries. This is because LIBDEF does not support authorized libraries.

### *XDCHELPM: Additional Considerations*

XDCHELPM is an overlay structured load module located in the `DBCOLE.XDCZ12.XDCLINK` library. As noted above, because it is overlay structured, it cannot be copied using ISPF's Move/Copy Utility (option 3.3). IEBCOPY must be used instead.

ADDITIONAL WARNING! Some customers have used IBM's Bulk Data Transfer product ("BDT") to move the `z/XDC` load modules between CPU's. This works fine for all load modules except XDCHELPM. Apparently, **BDT does not correctly reconstruct overlay structured load modules at the receiving CPU!** BDT does not issue any error messages, but the internal linkages between the overlay segments within XDCHELPM wind up being damaged! Accordingly, if you need to use BDT to ship XDCHELPM from one CPU to another, first use IEBCOPY to unload the module to a sequential dataset (as if you were dumping it to tape). Then you can use BDT to ship the unloaded module to the other CPU, and then you can use IEBCOPY at the receiving CPU to restore the module to its PDS format. Note, when using IEBCOPY to unload XDCHELPM from partitioned to sequential format, you do not need to specify a DCB for the output sequential dataset; IEBCOPY will set suitable values for you.

Alternatively: TSO's TRANSMIT and RECEIVE commands can be used without problems for shipping `z/XDC` load modules between computers (mainframes and/or PC's). That's because these commands automatically use IEBCOPY internally to convert partitioned datasets into a sequential format before sending them down the wire.

### *XDCCALLA and XDCCMDA: Additional Considerations*

XDCCALLA and XDCCMDA are authorized aliases of the XDCCALL load module located in the `DBCOLE.XDCZ12.XDCLINK` library. XDCCALL is a TSO command that allows a user to debug other commands and programs using `z/XDC`. (XDCCALL establishes an interface to `z/XDC` for the command or program being debugged.) The XDCCMDA and XDCCALLA alias names are intended for use by TSO users who wish to debug authorized command processors and other programs. These names have been created with the "AC=1" attribute. If you do not wish to permit authorized debugging, then you can create security system rules to prohibit it. See "*Defining z/XDC to Your Computer's Security System*" on page [29](#) for more information.

On the other hand, if you do want to permit authorized debugging via XDCCALLA and XDCCMDA, then you will have to tell TSO to let these two programs run authorized. (Otherwise, they will run non-authorized in TSO and, therefore, behave identically to XDCCALL and XDCCMD.) This is done by updating certain TSO tables.

To allow XDCCALLA and XDCCMDA to run authorized in TSO, you must add their names to the AUTHCMD parameter in the active `IKJTSOxx` member of `SYS1.PARMLIB`. Then in order to activate the new AUTHCMD list, you can either re-IPL or use TSO's "PARMLIB" command to cause TSO to refresh its AUTHCMD list on the fly, without an IPL. For details, see [Figure 11](#) on page [21](#). For more complete information, see IBM's **Initialization**

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Installing the Extended Debugging Controller)**

and Tuning Reference manual<sup>14</sup>, the TSO/E Customization manual<sup>15</sup> and the RACF Command Language Reference manual<sup>16</sup>.

Use an editor to add XDCCALLA and XDCCMDA to the list of names for the AUTHCMD parameter (found in the IKJTSoxx member of SYS1.PARMLIB):

```
AUTHCMD NAMES ( ...
                ...
                XDCCALLA XDCCMDA
                ...
                )
```

Use the "PARMLIB" TSO command to validity check and then activate your changed IKJTSoxx. The PARMLIB command can be issued either from TSO's "READY" prompt or from ISPF's option 6 panel.

- To validity check your change, type: **PARMLIB CHECK (xx)**
- To activate your change, type: **PARMLIB UPDATE (xx)**
- To display your change, type: **PARMLIB LIST (AUTHCMD)**

where "xx" matches the last two characters of the name of the IKJTSoxx member of SYS1.PARMLIB that you updated.

If system security does not permit you to use the PARMLIB command, then you need to have a security officer give you UPDATE authority to the "PARMLIB" resource of the "TSOAUTH" class. If your security system is RACF, then the following commands can be issued from TSO's "READY" prompt or from ISPF's Option 6 panel:

- To display the resource, type: **RLIST TSOAUTH PARMLIB ALL**
- To give a user UPDATE authority, type: **PERMIT PARMLIB CLASS (TSOAUTH) ACCESS (UPDATE) ID (userid)**

**Figure 11** Adding XDCCALLA and XDCCMDA to IKJTSoxx

Note that the above procedure is one of the steps needed to permit XDCCALLA and XDCCMDA to run authorized in TSO. XDCCALLA also can run in a batch job (// EXEC PGM=XDCCALLA,...). In this case, it is irrelevant whether or not XDCCALLA's name is in IKJTSoxx's AUTHCMD list, XDCCALLA will run authorized in the batch regardless. To control this use of XDCCALLA, you will have to define security system rules. See "*Defining z/XDC to Your Computer's Security System*" on page [29](#) for more information.

### *Adding XDCCLIST*

The DBCOLE.XDCZ12.XDCCLIST library contains two clists that are used in an ISPF interface to z/XDC. They are named XDCCLIST and XDCLBDEF.

- **XDCCLIST** is required. It is invoked internally by z/XDC's Startup Panel to allocate datasets prior to passing control to z/XDC.

<sup>14</sup>z/OS: SA22-7592. OS/390: SC28-1752. MVS/ESA: GC28-1635.

<sup>15</sup>z/OS: SA22-7783. OS/390: SC28-1965. MVS/ESA: SC28-1380.

<sup>16</sup>z/OS: SC22-7687. OS/390: SC28-1919. MVS/ESA: SC28-0733.

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Installing the Extended Debugging Controller)**

- **XDCLBDEF** is optional. It can be used if you wish to avoid adding the `DBCOLE.XDCZ12.XDCCLIST`, `DBCOLE.XDCZ12.XDCMLIB`, `DBCOLE.XDCZ12.XDCPLIB`, and `DBCOLE.XDCZ12.XDCTLIB` libraries to your TSO logon PROCs.

You may install these clists into your system in any of the following ways:

- You may copy both clists to an existing clist library.
- You may copy just the XDCLBDEF clist to an existing clist library and modify its default input parameters (the "CLIST(dsname)" operand) to point to the original library that contains the XDCCLIST clist.
- You may add the `DBCOLE.XDCZ12.XDCCLIST` library to your existing clist library concatenations.

Although the XDCCLIST and XDCLBDEF clists have been revised from one release to the next, they remain compatible with older XDC's and z/XDC's. Accordingly, if you have an older XDC or z/XDC installed, then you can and should replace the older XDCCLIST and XDCLBDEF with these newer versions.

If you copy the `DBCOLE.XDCZ12.XDCCLIST` library clists to an existing clist library, then be aware of the following:

- The `DBCOLE.XDCZ12.XDCCLIST` library is distributed with `RECFM=FB` and `LRECL=80`. The clists within it, however, are structured so that they can be copied to a `RECFM=VB` clist library without damage.
- If your target clist library has `RECFM=VB`, then you must use ISPF's Move/Copy Utility (option 3.3) to perform the copy. IEBCOPY cannot do the necessary record format conversion.
- This copying process will have to be repeated every time you apply z/XDC maintenance to the `DBCOLE.XDCZ12.XDCCLIST` library.

If you add the `DBCOLE.XDCZ12.XDCCLIST` library to your clist library concatenations:

- Your clist libraries must all be `RECFM=FB` and `LRECL=80`. z/OS does not support concatenations of libraries having differing record formats.
- You must add a DD card for the `DBCOLE.XDCZ12.XDCCLIST` library to the `//SYSPROC` concatenation of every logon PROC for every TSO user whom you expect to use z/XDC. (Note, systematic use of `"//INCLUDE ---" JCL` in your LOGON procs can ease this sort of burden considerably. See [z/OS MVS: JCL Reference](#)<sup>17</sup> for more information.)
- Alternatively, if you use logon clists (e.g. "PARM=%LOGON" in the TSO logon PROCs), you can recode that clist to add the `DBCOLE.XDCZ12.XDCCLIST` library to the `//SYSPROC` concatenations.
- It does not matter where, in the `//SYSPROC` concatenation, the `DBCOLE.XDCZ12.XDCCLIST` library occurs (first, last, middle) except that when an older XDC, XDC/SE, or z/XDC clist resides in the concatenation, then this newer library needs to be concatenated ahead of the older one.
- The first library in any concatenation either must have the largest `BLKSIZE` or must specify `DCB=BLKSIZE=` a value as large as or larger than the library having the largest `BLKSIZE`. The `DBCOLE.XDCZ12.XDCCLIST` library's `BLKSIZE` is 27920.

### *Adding XDCMLIB, XDCPLIB, and XDCTLIB*

The `DBCOLE.XDCZ12.XDCMLIB`, `DBCOLE.XDCZ12.XDCPLIB`, and `DBCOLE.XDCZ12.XDCTLIB` libraries contain ISPF panels, messages, and table modules used for interfacing z/XDC to ISPF. (See [Figure 12](#) on page 23.) You

---

<sup>17</sup>z/OS: SA22-7597. OS/390: GC28-1757.

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Installing the Extended Debugging Controller)**

may either copy these libraries to existing ISPF libraries, or you may add them to your existing library concatenations.

<b>z1.2*</b> <b>Name</b>	<b>S2.0</b> <b>Name</b>	<b>X3.3</b> <b>Name</b>	<b>Type</b>	<b>Purpose</b>
TFSXDC12	TFSXSE20	TFSXDC33	Table	A system-wide default profile for users.
TFSPROF	same	same	Table	An ISPF profile that causes ISPF to pass all PF-keys and ISPF commands through for processing by z/XDC.
XDCZ12A	XDCS20A	XDCT33A	Panel	A dynamic panel used for nearly all of z/XDC's displays when it is communicating to the user's terminal via ISPF's display service routines.
XDCZ12B	XDCS20B	XDCT33B	Panel	A special purpose panel used in miscellaneous situations by z/XDC's interface to ISPF.
XDCPANEL	same	same	Panel	z/XDC's Startup Panel to be installed into ISPF so that user's can more easily invoke z/XDC.
XDCPHELP	same	same	Panel	Online Help for z/XDC's Startup Panel (XDCPANEL).
XDCPHLPx	same	same	Panel	Various additional Online Help for z/XDC's Startup Panel.
XDCM00	same	same	Message	Error messages used by the z/XDC Startup Panel.
XDCCLIST	same	same	Clist	Invoked internally by XDCPANEL to allocate datasets and then call XDCCALL (et.al.) to start the requested debugging session.
XDCLBDEF	same	same	Clist	Can be invoked by users to dynamically allocate z/XDC's ISPF libraries and display the XDCPANEL panel.

\*Those objects whose names have not changed are backwards compatible with prior z/XDC releases.

**Figure 12** z/XDC's ISPF Clists, Panels, Tables, and Message Modules

Alternatively, you may avoid adding the DBCOLE.XDCZ12.XDCMLIB, DBCOLE.XDCZ12.XDCPLIB, and DBCOLE.XDCZ12.XDCTLIB libraries to your ISPF and other system libraries and instead use the XDCLBDEF clist to dynamically allocate these libraries only when a user wants to run z/XDC.

z/XDC's ISPF panels, tables, and message modules for release z1.2 have been updated from those used by prior versions or releases. Those elements that are no longer compatible with older XDC's and z/XDC's have been renamed, while those that remain compatible retain their old names. Accordingly, if you have an older XDC or z/XDC installed, then you can and should replace the older panels, tables, and message modules with these newer versions, but also retain those older elements not replaced by newer elements.

If you copy DBCOLE.XDCZ12.XDCMLIB, DBCOLE.XDCZ12.XDCPLIB, and DBCOLE.XDCZ12.XDCTLIB into existing ISPF libraries:

- This copying process will have to be repeated every time you apply z/XDC maintenance to the DBCOLE.XDCZ12.XDCMLIB, DBCOLE.XDCZ12.XDCPLIB, and DBCOLE.XDCZ12.XDCTLIB libraries.
- Modify an invoking panel (such as ISR@PRIM or ISRUTIL) to invoke the XDCPANEL panel. (See "Setting Up the XDCPANEL Panel or the XDCLBDEF Clist" below on page 24 for details.)

If you add the DBCOLE.XDCZ12.XDCMLIB, DBCOLE.XDCZ12.XDCPLIB, and DBCOLE.XDCZ12.XDCTLIB libraries to your ISPF library concatenations:

- You must add a DD card for the z/XDC libraries to the //ISPMLIB, //ISPPLIB, and //ISPTLIB

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Installing the Extended Debugging Controller)**

concatenations of every logon PROC for every TSO user whom you expect to use z/XDC. (Note, systematic use of "// INCLUDE ---" JCL in your LOGON procs can ease this sort of burden considerably. See [z/OS MVS: JCL Reference](#)<sup>18</sup> for more information.)

- Alternatively, if you use an ISPF startup clist, you can recode that clist to add the z/XDC libraries dynamically to the ISPF library concatenations.
- It does not matter where, in the ISPF library concatenations, the z/XDC libraries occur (first, last, middle) except that when older XDC or z/XDC elements reside in the concatenations, then these newer libraries need to be concatenated ahead of the older ones.
- The first library in any concatenation either must have the largest BLKSIZE or must specify DCB=BLKSIZE= a value as large as or larger than the library having the largest BLKSIZE. The z/XDC library BLKSIZEs are all 27920.
- Modify an invoking panel (such as ISR@PRIM or ISRUTIL) to invoke the XDCPANEL panel. (See "[Setting Up the XDCPANEL Panel or the XDCLBDEF Clist](#)" below on page [24](#) for details.)

If you use the XDCLBDEF clist to dynamically allocate DBCOLE.XDCZ12.XDCMLIB, DBCOLE.XDCZ12.XDCPLIB, DBCOLE.XDCZ12.XDCTLIB, and DBCOLE.XDCZ12.XDCCLIST libraries, then:

- Read the commentary within XDCLBDEF to understand how it works.
- Change the default values of the MLIB, PLIB, TLIB, and CLIST parameters (in the XDCLBDEF clist) to reference the actual dsnames of the DBCOLE.XDCZ12.XDCMLIB, DBCOLE.XDCZ12.XDCPLIB, DBCOLE.XDCZ12.XDCTLIB, and DBCOLE.XDCZ12.XDCCLIST libraries.
- You may nullify any of the MLIB, PLIB, TLIB, and CLIST parameters by coding an asterisk ("\*") for its value. Example: "CLIST(\*)" causes the XDCLBDEF clist not to allocate a DBCOLE.XDCZ12.XDCCLIST library and not to issue an ALTLIB ACTIVATE command for it.
- Optionally, you may modify an invoking panel (such as ISR@PRIM or ISRUTIL) to invoke the XDCLBDEF clist instead of the XDCPANEL panel. (See "[Setting Up the XDCPANEL Panel or the XDCLBDEF Clist](#)" below on page [24](#) for details.) Alternatively, the user can simply run the XDCLBDEF clist from ISPF's option 6.

### *Setting Up the XDCPANEL Panel or the XDCLBDEF Clist*

The XDCPANEL panel provides an interface allowing ISPF users a quick and easy way to invoke z/XDC to debug their programs. To make it available to your users, you need to choose an invoking panel (such as ISR@PRIM or ISRUTIL) and then modify it as shown in [Figure 13](#) on page [25](#).

XDCPANEL can be invoked either directly ("PANEL(XDCPANEL)") or indirectly ("CMD(%XDCLBDEF)"). See "[Choosing Between Using XDCPANEL Directly or Indirectly via XDCLBDEF](#)" on page [25](#) for important considerations.

In order to install XDCPANEL, see [Figure 13](#) on page [25](#) and proceed as follows:

- A line needs to be added to the calling panel's )BODY section to show the user what option code he needs to type to invoke the XDCPANEL panel. "D" is suggested. It stands for "Debugging". "X" is not recommended because that would conflict with ISPF's "exit" command.

---

<sup>18</sup>z/OS: SA22-7597. OS/390: GC28-1757.

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Installing the Extended Debugging Controller)**

```
)BODY
  ...
%   D +XDC           - Interactive Debugging with XDC
  ...

)PROC
  ...
  &ZSEL = TRANS( TRUNC (&ZCMD, '.')
    ...
    D, 'PANEL(XDCPANEL)'      ***or***      D, 'CMD(%XDCLBDEF)'
    ...
```

**Figure 13** ISPF Panel Mods for Invoking the XDCPANEL Panel

- A line needs to be added to the calling panel's &ZSEL=TRANS... command to invoke either the XDCPANEL panel or the XDCLBDEF clist, depending upon the considerations discussed below.

### *Choosing Between Installing XDCPANEL Directly or Indirectly via XDCLBDEF*

If you invoke "PANEL(XDCPANEL)":

- z/XDC's DBCOLE.XDCZ12.XDCPLIB, DBCOLE.XDCZ12.XDCMLIB, DBCOLE.XDCZ12.XDCTLIB, and DBCOLE.XDCZ12.XDCCLIST libraries must first be copied to or concatenated to your ISPLLIB, ISPMLIB, ISPTLIB, and SYSPROC libraries, as discussed above in "Adding XDCMLIB, XDCPLIB, and XDCTLIB" on page [22](#) and in "Adding XDCCLIST" on page [21](#).
- z/XDC's DBCOLE.XDCZ12.XDCLINK and DBCOLE.XDCZ12.XDCPLPA libraries must first be copied to or concatenated to your STEPLIB, PLPA, and/or link-libraries, as discussed above in "Adding XDCLINK" on page [18](#) and "Adding XDCPLPA" on page [18](#).

If you invoke "CMD(%XDCLBDEF)":

- You need not copy or add the DBCOLE.XDCZ12.XDCPLIB, DBCOLE.XDCZ12.XDCMLIB, DBCOLE.XDCZ12.XDCTLIB, and DBCOLE.XDCZ12.XDCCLIST libraries to your ISPF libraries. They will be dynamically allocated by XDCLBDEF.
- But you still have to copy the XDCLBDEF member of the DBCOLE.XDCZ12.XDCCLIST library to a SYSPROC library.
- For **non**authorized debugging, you need not add the DBCOLE.XDCZ12.XDCLINK and DBCOLE.XDCZ12.XDCPLPA libraries to your linklist, PLPA, or TSO STEPLIB libraries. Instead, you can name those libraries in XDCLBDEF's LLIB operand, and they will be dynamically allocated as ISPLLIB type libraries.
- However, for **authorized** debugging, naming the DBCOLE.XDCZ12.XDCLINK and DBCOLE.XDCZ12.XDCPLPA libraries via the LLIB operand will not work. This is because ISPF does not support authorized libraries via its ISPLLIB facility. Consequently, you will **STILL** have to copy or concatenate the DBCOLE.XDCZ12.XDCLINK and DBCOLE.XDCZ12.XDCPLPA libraries into your STEPLIB, PLPA, and/or link-libraries (as discussed in "Adding XDCLINK" on page [18](#) and "Adding XDCPLPA" on page [18](#)).
- Use of the XDCLBDEF clist makes it easier to offer multiple versions or releases of z/XDC to your ISPF users. Users can run the XDCLBDEF clist from ISPF's option 6.
- Alternatively, you can setup two options in an invoking ISPF panel: "D,'PANEL(XDCPANEL)'" to invoke

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Installing the Extended Debugging Controller)**

the old production version or release of z/XDC and "DNEW,'CMD(%XDCLBDEF)" to invoke the new z/XDC release during a "try-out" period.

### *Adding XDCCMDS*

The DBCOLE.XDCZ12.XDCCMDS library is a partitioned dataset containing sample streams of z/XDC commands ("scripts"). End users can use z/XDC's "READ" command to execute these scripts for various purposes. Accordingly, when you make z/XDC available to your users, please also publicize this library so that they will be able to use it. Also, when defining z/XDC to your security system (see "*Defining z/XDC to Your Computer's Security System*" on page [29](#)), be sure to give your users "read" access to this library.

### **Step 3: Re-IPL (Maybe)**

If you have taken any actions in the preceding steps that require an IPL, then now would be a good time to do so. Generally, you will need to re-IPL if you were unable to use the SETPROG command to compensate for any of the following occurrences:

- Placed the DBCOLE.XDCZ12.XDCPLPA library or its contents into the LPA-list. In this case you will have to IPL with CLPA specified.
- Added the DBCOLE.XDCZ12.XDCLINK and/or the DBCOLE.XDCZ12.XDCPLPA libraries to the linklist.
- Copied z/XDC load modules into an existing linklist library causing that library to expand into extra extents.
- Added the DBCOLE.XDCZ12.XDCLINK and/or DBCOLE.XDCZ12.XDCPLPA library to the APF section of a PROGxx member of SYS1.PARMLIB.
- Added the XDCCALLA and XDCCMDA names to the AUTHCMD list of an IKJTSOxx member of SYS1.PARMLIB and you are unable to use the "PARMLIB" command to update TSO on the fly.

If you need to IPL at this time but are unable to do so, you can still proceed with z/XDC installation subject to the following limitations:

- You may have to add z/XDC libraries to a TSO session's STEPLIB allocations in order to run z/XDC for licensing purposes, installation verification purposes, and SVC installation purposes.
- z/XDC may not be able to run authorized unless you temporarily copy z/XDC's load modules to an existing authorized library.
- If z/XDC cannot run authorized, then you will not be able to install z/XDC's service and hook SVCs at this time. (For now, not as big a deal as it sounds.)
- If z/XDC cannot run authorized, then you will not be able to test the installation of z/XDC's Cross Domain Facility.

### **Step 4: Defining Your License to Use z/XDC**

Before you can use z/XDC, you must define to it your license to use it on your current system. The License Definition process is entered by z/XDC automatically the first time that you try to use z/XDC. So in order to define your license to z/XDC, you must run z/XDC.

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Installing the Extended Debugging Controller)**

At this stage of the installation process you can run z/XDC as follows:

- Logon to a TSO terminal and proceed either to TSO's READY prompt or to ISPF's option 6 panel.
- The License Definition process is going to cause z/XDC to write to the XDCLCNSE load module on disk. Consequently, you must insure that your TSO userid has write access to the library containing that module.
- In order to run z/XDC, XDCCALL is going to need access to the XDC, XDC31, XDCTFS, and XDCLCNSE load modules. If any of the libraries containing these modules are not in TSO's or ISPF's search order, then use TSO's ALLOC command to allocate them to ddname TASKLIB. Example:

```
ALLOC FILE(TASKLIB) DA('DBCOLE.XDCZ12.XDCPLPA' 'DBCOLE.XDCZ12.XDCLINK')
REUSE SHR
```

Note, if you have placed z/XDC into an LPA-list library, and you have not yet CLPA'd, then you will have to allocate that library to TASKLIB as exemplated above. Similarly, if you have placed XDC, XDC31, XDCTFS, and XDCLCNSE into a new linklist library or into an existing linklist library but that library has expanded, and if you have not yet re-IPL'd, then again you will have to allocate that library to TASKLIB as exemplated above.

- From TSO READY or from ISPF option 6, start z/XDC as follows:
  - If the XDCCALL load module has already been installed into TSO's load module search order (linklist library, STEPLIB library, or ISPLLIB library), then type:

```
XDCCALL IEFBR14
```

- Otherwise, type:

```
CALL 'DBCOLE.XDCZ12.XDCLINK(XDCCALL)' 'IEFBR14'
```

- z/XDC may display some messages regarding the unavailability of its service SVCs. These can be disregarded at this point. Just press ENTER until a screen is displayed that is similar to the one shown in [Figure 14](#) on page [28](#).



# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Installing the Extended Debugging Controller)**

place. To avoid this problem, you must issue the following system operator command: **F LLA,REFRESH**

- Similarly, if your data center uses a caching product from Computer Associates called "PMO" with "QFETCH", and if the load library containing the XDCLCNSE module is cached by that product, then you will have to issue the following command to cause that product to refresh its image of the load library:  
**F PMO,D=libdsn**
- If the Licensing Control Data is rejected, z/XDC will continue to display its License Definition Panel. You may make any corrections that are necessary and then attempt to issue the END command again. Alternatively, you may type CANCEL to terminate z/XDC immediately. In this case, z/XDC does not write the LCD to XDCLCNSE. You should then call Cole Software (540-456-8210) for assistance in determining what the problem is.

Once you have successfully defined your license to z/XDC, you will be able to run debugging sessions. If at some future time you need to display the License Definition Panel again, you can do so by starting a normal z/XDC debugging session (such as "XDCCALL IEFBR14") and then issuing the "LICENSE" command.

After you have finished the license definition process, you should then IEBCOPY the XDCLCNSE load module from your production library back to your SMP/E target library (DBCOLE.XDCZ12.XDCLINK) and to your SMP/E DLIB library (DBCOLE.XDCZ12.XDCDLIB.XDCDLINK). Doing this will avoid problems in the future when you apply new maintenance and then decide to mass-copy all of z/XDC's load modules from the target library over to your production libraries.

If you are installing multiple copies of z/XDC into multiple z/OS images, then after performing the licensing procedure for the first copy, you can IEBCOPY the modified XDCLCNSE load module over to the other copies of z/XDC. This will work so long as all copies require the same Licensing Control Data.

### **Step 5: Defining z/XDC to Your Computer's Security System**

z/XDC is a generalized debugging tool that can be a powerful aid to any assembler language programmer. z/XDC, in and of itself, is not "authorized"; accordingly, z/XDC both can and should be made available to a computer center's general TSO user population. In a secured computer center, a general user cannot violate system integrity with z/XDC.

There are, however, certain circumstances under which an installation may wish to restrict use of z/XDC to authorized personnel only:

- 1.) When a z/XDC interface is installed into an authorized program, z/XDC may be given control in an authorized mode by that program. When this happens, the user of z/XDC can zap arbitrary system storage. Note that in a properly secured computer center, only appropriate personnel will have the capability of installing a z/XDC interface into an authorized program.
- 2.) When z/XDC is running authorized, the user may be permitted to use z/XDC commands (such as "SET ASID" or "HOOK") to gain access to other address spaces. When a user has such access to a foreign address space, z/XDC may permit him to display and possibly to zap any data in that address space.
- 3.) When a user logs onto z/XDC's Cross Domain Facility, system security is called to verify that user's identity and again to determine which background jobs or tasks he is permitted to connect to for debugging.

If you need to control these kinds of accesses, then you will need to install certain z/XDC defined access control rules into your security system.

*For More Information About z/XDC Security ...*

The following pages describe what kinds of security restrictions can be set up for z/XDC users and how to

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Installing the Extended Debugging Controller)**

establish those restrictions. If you are interested, there also is available a comprehensive discussion of general security issues and questions raised by a product such as z/XDC. You can read this discussion either in [z/XDC z1.2 User's Guide](#) or in z/XDC's Online Help. The title of the discussion is named "Help Security". To read it, start a z/XDC debugging session<sup>19</sup>, and then type "HELP SECURITY".

### *z/XDC's Standard Security Method*

z/XDC issues calls to the installation's own security system via IBM's "System Authorization Facility" (i.e. the "SAF interface", a standard facility in all z/OS systems, secured or otherwise). z/XDC makes such calls whenever the user first attempts to use a z/XDC command that may give rise to a security concern. Specifically, z/XDC calls security under the following circumstances:

- 1.) Upon the first use within a debugging session of z/XDC in an authorized mode, z/XDC checks for "READ" access to a z/XDC defined resource named "XDC.AUTH".
- 2.) The first time that a "SET ASID" command or an addressing function (such as "~ASID(...)") is used to gain read access to another address space. If that address space does not have an ownerid<sup>20</sup> that matches the ownerid of the address space from which the "SET ASID" command is being issued, then z/XDC checks for "READ" access to a resource named "XDC.FASM.jobname" (where "jobname" is the name of the address space being accessed). This call is made for each different address space so accessed.
- 3.) The first time that a storage altering command (ZAP, etc.) is used to alter the private area of another address space (and if that address space has a different ownerid than the home space), z/XDC checks for "UPDATE" access to the "XDC.FASM.jobname" resource.
- 4.) Any time that a storage altering command is used to alter any storage anywhere, z/XDC checks for "UPDATE" access to a resource named "XDC.ZAP.---" (where "---" more specifically describes the storage to be altered). Note, this check will be made even for zaps that also require the check for UPDATE access to the "XDC.FASM.jobname" resource. (For more information, see HELP SECURITY ZAP either in z/XDC's Online Help or in [z/XDC z1.2 User's Guide](#).)
- 5.) When a user signs onto the Cross Domain Facility from an idle VTAM terminal, CDF calls security to verify that user's id and password. (When a user signs onto CDF from a TSO session, no password check is necessary because the user's id and password have already been verified when the user first signed onto TSO.)
- 6.) When a user who has signed onto CDF selects a background job or task to debug, if that job's ownerid does not match the user's userid, then CDF calls security to see if that user is authorized to debug the selected job or task. It checks for "UPDATE" access to the appropriate "XDC.FASM.jobname" resource.

Important: For more detailed descriptions of z/XDC's resource access control rules, see the HELP SECURITY topic in [z/XDC z1.2 User's Guide](#) or in z/XDC's Online Help.

### *Using z/XDC Prior to Creating Security Definitions*

z/XDC's security interface explicitly supports three security systems: RACF, CA-ACF2, and CA-Top Secret. This support requires various implementing definitions be made within the security systems as described in the following sections. Until such definitions are made, the RACF and CA-Top Secret security systems report the various z/XDC resources as being "unprotected" (RC=4 from the RACROUTE macro), and z/XDC treats such responses as being equivalent to a "permit" response (RC=0). Accordingly, in RACF and CA-Top Secret shops z/XDC can be installed and testing during a trial period without having to setup security definitions, but security

---

<sup>19</sup>From TSO's READY prompt or from ISPF's Option =6, type "XDCCALL IEFBR14".

<sup>20</sup>z/XDC finds an address space's "ownerid" by looking in the ACEEUSRI field of that address space's ACEE control block. If the ACEE does not exist, or if the ACEEUSRI field contains blanks or an asterisk, then z/XDC concludes that the address space does not have an ownerid.

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Installing the Extended Debugging Controller)**

concerned installations should make the necessary definitions prior to z/XDC's being released to the user community for general use.

Exceptions:

- RACF: When RACF is installed on a system, and that system still uses `SYS1.UADS` to control TSO logons, if a program (such as z/XDC's Cross Domain Facility) asks RACF to validity check a given userid, RACF's return code is 4 (not 8). This is RACF's way of saying, "I don't know this guy. Ya gotta check UADS". XDC-CDF, unfortunately, does not have code that can access `SYS1.UADS`, and so XDC-CDF will fail the logon attempt. There are workarounds:
  - Set XDC-CDF's "NOVALIDATE" option via either a System Operator's MODIFY command or a `SYSIN` input parameter. For more information, see the `XCDFPARM` member of the `DBCOLE.XDCZ12.XDCCDF` library.
  - User's can still connect to XDC-CDF from ISPF via the "z/XDC Startup Panel" (the `XDCPANEL` member of the `DBCOLE.XDCZ12.XDCPLIB` library).
- CA-ACF2: CA-ACF2 "disallows" (RC=8 from the `RACROUTE` macro) accesses to unprotected resources; therefore, in CA-ACF2 shops suitable security definitions for z/XDC will have to be made before z/XDC can be used fully.

### *Using z/XDC in RACF Protected Systems*

[Figure 15](#) on page [32](#) shows the `RACROUTE` macro operands used by z/XDC in RACF protected systems. Note that z/XDC uses the resource class named "FACILITY". This is an IBM defined "catch-all" class used to control accesses to miscellaneous system facilities. IBM uses this class for controlling storage dumps, access to vector processors, logon passwords for JES2/3 RJE/RJP and NJE connections, and miscellaneous facilities in various program products. z/XDC's use of this class avoids the necessity of requiring the customer to create or modify a "user" Class Descriptor Table.

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Installing the Extended Debugging Controller)**

<b>Call Type</b>	<b>ATTR=</b>	<b>ENTITY Value</b>	<b>Resource Class</b>
Authorized mode	READ	CL44 'XDC.AUTH'	FACILITY
Read a foreign address space	READ	CL44 'XDC.FASM.asname' *	FACILITY
Zap a foreign address space	UPDATE	CL44 'XDC.FASM.asname' *	FACILITY
Debug a program via CDF	UPDATE	CL44 'XDC.FASM.asname' *	FACILITY
Zap storage	UPDATE	CL44 'XDC.ZAP.---'	FACILITY

\*"Asname" is replaced by the 8-character name of the address space that the user is trying to access.

\*\*Zaps that require permission under the "XDC.FASM.asname" rule, still also require permission under an appropriate "XDC.ZAP.---" rule.

The value "XDC" is used for security calls regardless of z/XDC's name. (See "Renaming z/XDC" on page 15 for more information.)

For RACF protected systems, z/XDC issues the RACROUTE macro with "REQUEST=AUTH" and with REQSTOR and SUBSYS not set. Example: An attempt by a user to zap JES2's address space would cause z/XDC to issue the following RACROUTE macro:

```
RACROUTE REQUEST=AUTH,ATTR=UPDATE,CLASS=CLASS-1,
          ENTITY=RESOURCE

CLASS    DC    AL1 (L'CLASS)
CLASS    DC    C'FACILITY'
RESOURCE DC    CL44 'XDC.FASM.JES2'
```

**Figure 15** RACROUTE Macro Operands Used by z/XDC in RACF Protected Systems

To implement z/XDC security, a security officer should do the following:

- Use RACF's RDEFINE command (as follows) to create in the FACILITY class default profiles prohibiting access to all of z/XDC's authorized facilities for all users:

```
RDEFINE FACILITY XDC.AUTH UACC(NONE)
RDEFINE FACILITY XDC.ZAP.* UACC(NONE)
RDEFINE FACILITY XDC.FASM.* UACC(NONE)
SETROPTS REFRESH RACLIST(FACILITY)
```

Use the characters "XDC" in these definitions regardless of whether or not you have renamed z/XDC. (See "Renaming z/XDC" on page 15 for more information.)

- Depending on your specific circumstances, you may have to issue one or more of the following commands to properly activate the FACILITY class:

```
SETROPTS CLASSACT(FACILITY)
If this class has not previously been activated on your system.
```

```
SETROPTS GENERIC(FACILITY)
Because "XDC.FASM.*" and "XDC.ZAP.*" are generic profiles.
```

```
SETROPTS RACLIST(FACILITY)
To boost RACF performance when scanning generic profiles.
```

- Use RACF's "PERMIT" command to give the XDCCDF job READ access to the XDC.AUTH rule:  
PERMIT XDC.AUTH CLASS(FACILITY) ID(ownerid) ACCESS(READ)  
Where "ownerid" is the RACF ownerid under which the XDCCDF job will execute.

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Installing the Extended Debugging Controller)**

- Use RACF's "PERMIT" command and additional "RDEFINE" commands to grant individual users and user groups accesses to z/XDC's various authorized facilities. Example: The following commands permit user DBCOLE to use z/XDC's Foreign Address Space Mode to display but not to zap JES2's private areas.

```
RDEFINE FACILITY XDC.FASM.JES2 UACC(NONE)
PERMIT XDC.FASM.JES2 CLASS(FACILITY) ID(DBCOLE) ACCESS(READ)
```

- Use the SETROPTS command to refresh the changes made to the facility class:

```
SETROPTS RACLIST(FACILITY) REFRESH
RLIST FACILITY *
```

For additional information, please refer to RACF's [Security Administrator's Guide](#)<sup>21</sup> and to its [Command Language Reference](#)<sup>22</sup>.

Also, for a comprehensive discussion about creating the XDC.AUTH, XDC.ZAP.---, and XDC.FASM.--- rules and about how z/XDC uses them, see the HELP SECURITY topic in [z/XDC z1.2 User's Guide](#) or in z/XDC's Online Help.

### *Using z/XDC in CA-ACF2 (Release 5.0 and Newer) Protected Systems*

[Figure 16](#) on page [34](#) shows the RACROUTE macro operands used by z/XDC in CA-ACF2 protected systems. To implement z/XDC security, several control definitions need to be made within CA-ACF2:

- An "XDC/XDC" entry needs to be added to the SAFMAPS control record.
- A "D-RXDC" entry needs to be added to the RESDIR control record.
- A SAFPROT.XDC control record needs to be created further defining the "XDC" class.
- Suitable "generalized resource rules" with TYPE(XDC) need to be created.<sup>23</sup>
- An "xxxCDF"<sup>24</sup> logonid needs to be created for the Cross Domain Facility. This id must be assigned at least the following attributes: MUSASS, STC, and RESTRICT.

---

<sup>21</sup>z/OS: SA22-7683. OS/390: SC28-1915. MVS/ESA: SC28-1340.

<sup>22</sup>z/OS: SC22-7687. OS/390: SC28-1919. MVS/ESA: SC28-0733.

<sup>23</sup>The name of the class, the SAFPROT record, the generalized resource rule type, and the RESDIR entry all must be "XDC" regardless of whether or not z/XDC has been renamed (as discussed above in "[Step 1: Renaming z/XDC](#)" on page [15](#)).

<sup>24</sup>Where "xxx" matches z/XDC's name.

# z/XDC® z1.2 INSTALLATION GUIDE

## (Installing the Extended Debugging Controller)

Call Type	ATTR=	ENTITY Value	CLASS, REQSTOR, and SUBSYS Values
Authorized mode	READ	CL44 'AUTH'	XDC
Read a foreign address space	READ	CL44 'FASM.asname' *	XDC
Zap a foreign address space**	UPDATE	CL44 'FASM.asname' *	XDC
Debug a program via CDF	UPDATE	CL44 'FASM.asname' *	XDC
Zap storage**	UPDATE	CL44 'ZAP. ---'	XDC

\*"Asname" is replaced by the 8-character name of the address space that the user is trying to access.

\*\*Zaps that require permission under the "XDC.FASM.asname" rule, still also require permission under an appropriate "XDC.ZAP.---" rule.

The CLASS, REQSTOR, and SUBSYS value of "XDC" must be used for security calls regardless of whether or not you have renamed z/XDC. (See "*Renaming z/XDC*" on page [15](#) for more information.)

CA-ACF2 Example: An attempt by a user to zap JES2's address space would cause z/XDC to issue the following RACROUTE macro:

```

RACROUTE REQUEST=AUTH,ATTR=UPDATE,REQSTOR=XDC,
          SUBSYS=XDC,CLASS=CLASS-1,ENTITY=RESOURCE

CLASS    DC    AL1 (L'CLASS)
CLASS    DC    C'XDC'
RESOURCE DC    CL44 'FASM.JES2'
XDC      DC    CL8 'XDC'
```

**Figure 16** RACROUTE Macro Operands Used by z/XDC in CA-ACF2 Protected Systems

More specifically, a security officer needs to modify the CA-ACF2 control records as follows:

- From TSO, type "ACF", then type "SET CONTROL(GSO)".
- List the "SAFMAPS" control record, then add "XDC/XDC" to the MAPS field of that record.
- Add the following to the "SAFPROT" control records:

```
SAFPROT.XDC CLASSES (-) CNTLPTS (-) SUBSYS (XDC)
```

- List the "OPTS" control record and insure that "SAF" is set. IMPORTANT! If you are not familiar with CA-ACF2's use of the SAF interface and with the effects of enabling SAF support within CA-ACF2, then refer to the "**ACF2/SAF Interface**" chapter of CA-ACF2's **System Programmer's Guide** for a detailed discussion of the implications to be considered.
- You will probably want "to mask" (i.e. use wildcard characters in) some of the z/XDC resource rule definitions you will be creating. Accordingly, a "directory" for the z/XDC rules will have to be made resident in system storage. To do so, start by listing the "RESDIR" control record. Then add "D-XDC" to the "TYPES" field.
- Finally, from an operator's console issue the CA-ACF2 commands necessary to "refresh" the control records you have modified (SAFMAPS, SAFPROT, OPTS, and/or RESDIR). This will activate the changes you have made.

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Installing the Extended Debugging Controller)**

Once "XDC" has been defined for the ACF2/SAF interface, it is now necessary to define the actual generalized resource rules that make up the "XDC" class. A CA-ACF2 security officer should do this as follows:

- From TSO, type "ACF", then type "SET RESOURCE(XDC)".
- Use CA-ACF2's COMPILE and other commands to create the desired access control rules. The rules should all specify "TYPE(XDC)".
- The "\$KEY" values for the various rules should be based on the following:

**\$KEY(AUTH) TYPE(XDC)**  
Controls use of z/XDC in authorized mode.

**\$KEY(ZAP.descriptions) TYPE(XDC)**  
Controls who can zap what storage. See the HELP SECURITY topic in [z/XDC z1.2 User's Guide](#) or in z/XDC's Online Help for details concerning "descriptions".

**\$KEY(FASM.asname) TYPE(XDC)**  
UID(. . .) SERVICE(READ)  
Controls who can have "read" access to the foreign address space named "asname".

**\$KEY(FASM.asname) TYPE(XDC)**  
UID(. . .) SERVICE(UPDATE)  
Controls who can have "zap" access and CDF access to the foreign address space named "asname".

- CA-ACF2 permits \$KEY values to contain "wildcard" characters (asterisks), thus it is possible, for example, to create one "FASM.asname" rule to control accesses to multiple address spaces. (CA-ACF2 refers to the use of wildcards as "masking"). Remember however, if such generic keys are to be used, then the "directory" for the "XDC" rules must be made "resident" in storage. This is done via the RESDIR control record (see above).

CA-ACF2 has an optional table of permitted TSO commands (both authorized and nonauthorized). If present, then that table needs to have entries added to it for XDCCALL XDCCMD XDCCALLA XDCCMDA XDCTFS and XDC.

Finally, in order to run the Cross Domain Facility's router task (see "*Installing z/XDC's Cross Domain Facility (CDF)*" on page 49), you will need to create a logonid for it with at least the following attributes: MUSASS, STC, and RESTRICT. The name of this logonid should be "xxxCDF"<sup>25</sup>, and that name must match the name of the PROC used to start the CDF router. You also must give the xxxCDF logonid READ access to the AUTH rule. **Note:** If your site has system task security turned off ("NOSTC" specified in the OPTS control record), then you will have to run xxxCDF as a batch job; you will not be able to run it successfully as a system task.

See CA-ACF2's [Administrator's Guide](#) for more information about defining generalized resource rules, about logonids, and about modifying the control records. Also, member ACF2SAMP in DBCOLE.XDCZ12.XDCSAMP contains several examples of various z/XDC type generalized resource rules.

Also, for a comprehensive discussion about creating the AUTH, ZAP.--, and FASM.-- rules and about how z/XDC uses them, see the HELP SECURITY topic in [z/XDC z1.2 User's Guide](#) or in z/XDC's Online Help.

### *Using z/XDC in CA-Top Secret Protected Systems*

[Figure 17](#) on page 36 shows the RACROUTE macro operands used by z/XDC in CA-Top Secret protected systems. Note that z/XDC uses the resource class named "XDC" regardless of z/XDC's actual name. Accordingly, a "system facility", an "ACID" ("access id"), and a "resource" all must be defined in TSS ("Top Secret Security")

---

<sup>25</sup>Where "xxx" matches z/XDC's name.

# z/XDC® z1.2 INSTALLATION GUIDE

## (Installing the Extended Debugging Controller)

as follows:

- Start by renaming a spare facility to "XDCCDF". Then assign it the attributes necessary to permit z/XDC's Cross Domain Facility to operate as a multi-user subsystem. (In order to make these changes permanent, you will have to update TSS's startup parms):

```
TSS MODIFY FAC (USERx=NAME=XDCCDF)
TSS MODIFY FAC (XDCCDF=PGM=XDCTFS, NOABEND, TENV26, MULTIUSER, NONPWR, NOTSOC)
```

Call Type	ATTR=	ENTITY Value	Resource Class
Authorized mode	READ	CL44 'AUTH'	XDC
Read a foreign address space	READ	CL44 'FASM.asname' *	XDC
Zap a foreign address space**	UPDATE	CL44 'FASM.asname' *	XDC
Debug a program via CDF	UPDATE	CL44 'FASM.asname' *	XDC
Zap storage*	UPDATE	CL44 'ZAP. ---'	XDC

\*"Asname" is replaced by the 8-character name of the address space that the user is trying to access.

\*\*Zaps that require permission under the "XDC.FASM.asname" rule, still also require permission under an appropriate "XDC.ZAP.---" rule.

The Resource Class of "XDC" is used for security calls regardless of z/XDC's name. (See "*Renaming z/XDC*" on page 15 for more information.)

For CA-Top Secret protected systems, z/XDC issues the RACROUTE macro with "REQUEST=AUTH" and with REQSTOR and SUBSYS not set. Example: An attempt by a user to zap JES2's address space would cause z/XDC to issue the following RACROUTE macro:

```
RACROUTE REQUEST=AUTH, ATTR=UPDATE, CLASS=CLASS-1,
          ENTITY=RESOURCE

CLASS    DC    AL1 (L' CLASS)
RESOURCE DC    C' XDC '
          DC    CL44 ' FASM. JES2 '
```

**Figure 17** RACROUTE Macro Operands Used by z/XDC in **CA-Top Secret** Protected Systems

- Create an ACID ("access id") named "XDCCDF". This will be the ACID assigned to the Cross Domain Facility's startup proc:

```
TSS CREATE (XDCCDF) NAME ('name') DEPT (ownerid) PASS (NOPW) FAC (STC, TSO)
          MASTFAC (XDCCDF)
```

- Assign xxxCDF's<sup>27</sup> startup PROC to use the XDCCDF ACID:

```
TSS ADD (STC) PROC (xxxCDF)28 ACID (XDCCDF)
```

<sup>26</sup>Support for "TENV" has been dropped in release 4.3 of TSS. Therefore, this operand should be omitted if you are running a 4.3 or newer release of TSS.

<sup>27</sup>Where "xxx" matches z/XDC's name.

<sup>28</sup>In TSS release 4.3, and in TSS release 4.2 with fix #552 applied, the program executed by the xxxCDF PROC will be able to use the XDCCDF "facility" regardless of whether or not the name of the program invoked by the PROC matches the "PGM=XDCTFS" parameter in the "facility" definition. In TSS release 4.2 systems with fix #552 not applied, then the program executed by the xxxCDF PROC must match the "PGM=XDCTFS" parameter in the "facility" definition.

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Installing the Extended Debugging Controller)**

- Allow users to logon to xxxCDF:  
`TSS ADD(userid) FAC(XDCCDF)`
- Define a resource named "XDC" in the RDT ("Resource Definition Table"). "RESCODE" may specify any previously unused 2-digit code:  
`TSS ADD(RDT) RESCLASS(XDC) RESCODE(hexcode) ATTR(DEFPROT, LONG) ACLST(NONE, READ, UPDATE)`

Note, starting with R4.4, CA-Top Secret has been shipping with the "XDC" resource class predefined. Unfortunately, at first they got it wrong! Among other things, they assigned the z/XDC resource class an attribute of "SHORT", while z/XDC actually requires that the class's attribute be "LONG".

Anyway, Computer Associates eventually discovered their errors, and so they developed the following fixes. These TSS fixes are required for using z/XDC in a CA-Top Secret environment:

- PTF GO64801 (available on the 9506 maintenance tape) replaces module TSSRTAB. It corrects the z/XDC class's length attribute from SHORT to LONG.
- APAR BB15253 corrects an "invalid keyword" error that occurs with the "TSS ADD(ownerid) XDC(rulename)" command.

Presumably, R5.0 and newer releases of CA-Top Secret come with the "XDC" resource predefined correctly. To summarize:

- If you are using a release of CA-Top Secret that is older than R4.4, then you have to issue the "TSS ADD" command shown above.
  - If you are using R4.4 or any newer release of CA-Top Secret, then you do not have to issue the "TSS ADD" command.
  - But if you are experiencing problems with installing z/XDC's definitions into TSS, then you will have to apply the TSS maintenance described above.
- Assign ownership to the various entity values that z/XDC uses in its security checks:  
`TSS ADD(ownerid) XDC(AUTH)`  
`TSS ADD(ownerid) XDC(ZAP.)`  
`TSS ADD(ownerid) XDC(FASM.)`  
If these commands fail with an "INVALID KEYWORD" message, then apply the TSS maintenance described above, and then try again.
  - Allow users to access the various resources secured by z/XDC. Example: The following commands permit user DBCOLE to use z/XDC's Foreign Address Space Mode to have both display, alter, and CDF access to JES2's private areas:  
`TSS PERMIT(DBCOLE) XDC(FASM.JES2) ACCESS(READ)`  
`TSS PERMIT(DBCOLE) XDC(FASM.JES2) ACCESS(UPDATE)`

Note that with CA-Top Secret (unlike other security systems) UPDATE access does not include or imply READ access. To permit both accesses, both accesses must be explicitly defined.

For additional information, please refer to TSS's **MVS Control Options Guide**, **MVS Implementation, Concepts and Facilities**, and **TSS Command Functions Guide**.

Also, for a comprehensive discussion about creating the AUTH, ZAP.---, and FASM.--- rules and about how z/XDC uses them, see the HELP SECURITY topic in **z/XDC z1.2 User's Guide** or in z/XDC's Online Help.

### *Another Approach to z/XDC Security*

If you are installing z/XDC for the exclusive use of non-authorized users, and if you are not interested in using the Cross Domain Facility for debugging background jobs, then you might consider a less complicated approach to z/XDC security. Simply place all of z/XDC's load modules into a non-authorized JOBLIB, STEPLIB, or linklist library (with LNKAUTH=APFTAB specified in the active IEASYSxx member of SYS1.PARMLIB). This will make

# **z/XDC® z1.2 INSTALLATION GUIDE**

## **(Installing the Extended Debugging Controller)**

it impossible for z/XDC to be invoked by an authorized program. In addition you may want to use normal system security dataset access rules to control who among the non-authorized users may or may not use z/XDC.

However, if you wish to install z/XDC's service SVCs (highly recommended, see "*Installing z/XDC's Service and Hook SVC ...*" below on page [38](#)), then you will still have to make a second copy of the z/XDC load modules and place them into an authorized library for use by the XDCINITc job (see below). Just be sure to use system security dataset access rules to make the authorized library non-executable by all users except the XDCINITc job.

### **Step 6: Installing z/XDC's Service and Hook SVCs (via the XDCINITc Job)**

In order to make the full range of z/XDC's facilities available for use, two special SVCs and several system intercepts must be installed for z/XDC. These SVCs provide various services that help improve the power of z/XDC. The SVCs do **not**, however, in any way enable z/XDC to run authorized. (z/XDC will run authorized only when it is invoked by a program that itself is already authorized). Considerable care has been exercised in the design of z/XDC's SVCs. They cannot be misused by **un**authorized callers to subvert system security or integrity.

z/XDC can be used without installing the SVCs; however, many of its capabilities will be somewhat limited. See "*Running z/XDC Without Its Service and Hook SVCs*" below on page [39](#) for specifics.

z/XDC's SVCs need not, and in fact cannot, be installed by the normal methods. Instead, they must be dynamically installed after every IPL by a special XDCINITc PROC that must be executed at or after IPL time. The XDCINITc PROC is shown in [Figure 18](#) on page [38](#). A copy of it can be found in DBCOLE.XDCZ12.XDCJCL

. This PROC must be placed into a system PROC-library (such as SYS1.PROCLIB).

#### **The xxxINITc Proc**

```
//*  
//xxxINITc EXEC PGM=xxxCALLA, PARM=IEFBR14, TIME=1
```

#### **The Associated SYS1.PARMLIB (COMMNDxx) Command**

```
COM='S xxxINITc'
```

Where xxx matches z/XDC's name (usually "XDC"), and where "c" can be any alphanumeric (or omitted) character.

**Figure 18** XDCINITc PROC and Associated COMMNDxx Command

Normally, the PROC must be named "XDCINIT" or "XDCINITc", where "c" can be any alphanumeric character. (See "*What the XDCINITc Job Does*" below on page [39](#), [42](#), [42](#) for why.) However, if you have renamed z/XDC to Z12, DBC, or some other name (see "*Renaming z/XDC*" on page [15](#)), then both the name of the XDCINITc PROC and the reference within the PROC to "XDCCALLA" must also be similarly renamed.

In order to insure that XDCINITc is executed on every IPL, you should add the command shown in [Figure 18](#) on page [38](#) to the active COMMNDxx member of SYS1.PARMLIB. Again, if z/XDC has been renamed, then the command's reference to XDCINITc should be similarly changed. See IBM's [Initialization and Tuning Reference manual](#)<sup>29</sup> for detailed discussions of SYS1.PARMLIB members.

<sup>29</sup>z/OS: SA22-7592. OS/390: SC28-1752. MVS/ESA: GC28-1635.

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Installing the Extended Debugging Controller)**

### *What the XDCINITc Job Does*

The XDCINITc job does little more than invoke z/XDC in an authorized mode. Whenever z/XDC runs authorized, it checks to see if its service SVC, its hook SVC, and its several system intercepts are installed. If any elements are either not installed or are at a maintenance level that is older than XDC itself, then those elements that need it are either installed or reinstalled.

In the case of the two SVCs, z/XDC automatically selects two available SVC numbers (199 and 198 or lower<sup>30</sup>), and it assigns them to the SVCs. (Usually, the hook SVC will be assigned to SVC #199, and the service SVC will be assigned to SVC #198, but this is not guaranteed.)

When (re)installation of the system interface is completed, z/XDC issues a detailed System Interface Initialization Report (messages DBC514I) showing exactly what it was and was not able to do, and why.

During the SVC installation process, z/XDC also does the following:

- It builds for itself a subsystem control table (SSCT) named "XDCc" (where "c" is a release specific special character) and uses it, among other things, as a place to save its SVC numbers.
- It installs various other system routines to support deferred breakpoints (see the HELP BREAKPOINTS DEFERRED topic in ***z/XDC z1.2 User's Guide*** or in z/XDC's Online Help) and certain end-of-task and end-of-memory cleanup functions.

If z/XDC is invoked in a job or system task whose name is "XDCINITc", then after insuring that its service and hook SVCs are installed, it terminates without entering into a debugging session. Thus, it is important that the XDCINITc job that is run at IPL time be named "XDCINITc" (or "xxxINITc" if z/XDC has been renamed to xxx). Otherwise, a spurious interactive debugging session will be started at the operator's console at IPL time (generally **not** a desirable occurrence).

### *Running XDCINITc Jobs for Multiple Versions and Releases of XDC*

If you are installing this z1.2 release of z/XDC to run in parallel with an older version or release of z/XDC, then you will have to have two XDCINIT jobs on your system, one for installing z1.2's SVCs and one for installing the older XDC or z/XDC's SVCs. To facilitate running multiple XDCINIT PROCs, a suffix character can be added to the PROC name. Therefore, it is suggested that z1.2's XDCINIT job be named "XDCINIT2".

### *Running z/XDC Without Its Service and Hook SVCs*

If z/XDC is invoked non-authorized and prior to its service and hook SVCs being installed, then it proceeds, but there will be several limitations to what it can do, including the following:

- Multiple calls to z/XDC from separate tasks within an address space will be unaware of each other's existence. They will not be able to share maps, equates, breakpoints, etc. This creates severe problems when you attempt to use z/XDC to debug multi-tasking programs. Accordingly, if you wish to debug multi-tasking programs, then you must install the service SVC.
- z/XDC's service SVC often is required during user program resumption (via z/XDC's GO or TRACE command) to properly restore some characteristics of the retry-level execution environment. If the service SVC is not installed, then certain retry-level restorations cannot occur. For example, if the user program uses the BAKR instruction to create entries in the system's Linkage Stack, then the GO and TRACE commands will not be usable so long as such stack entries exist.
- If you attempt to invoke z/XDC on both sides of an ISPF split screen session in TSO, your TSO session

---

<sup>30</sup>SVC numbers lower than 200 are chosen so as not to interfere with other user SVCs.

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Installing the Extended Debugging Controller)**

will become deadlocked and you will have to ask Operations to cancel your userid.

- Deferred breakpoint support depends upon various services provided by z/XDC's service SVC; accordingly, without the SVC, deferred breakpointing commands cannot be used.
- Users will be unable to use z/XDC's "HOOK" command (for dynamically creating z/XDC debugging sessions in other RB's, tasks, or address spaces).
- z/XDC will not be able to automatically detect when its displays are corrupted by TPUT's from the program being debugged.
- Use of the attention key during z/XDC processing will more frequently lead to keyboard lockouts requiring cancelation of the user's TSO session.
- Recognition, during tracing, of transfers to EODAD and SYNAD routines will not work.
- Handshaking with L.E.'s error recovery will not occur.

### **Step 7: The Installation Verification Test**

The Installation Verification Test can now be done in TSO. First, logon to TSO, and then start up ISPF. Then use one of the following methods to start z/XDC, depending upon how you have installed the product:

**Go to z/XDC's Startup Panel, fill it in as shown in [Figure 19](#) on page 40, and press ENTER.**

This will work if you have installed z/XDC's Startup Panel into ISPF. Note, if you have renamed z/XDC (see "*Renaming z/XDC*" on page 15), then the first thing you have to do is type z/XDC's new name (**DBC**, for example) on the command line and press ENTER. This will automatically reconfigure the panel to use the renamed z/XDC.

```
----- z/XDC STARTUP PANEL -----
OPTION  ==> 2                                XDC's name ==> XDC
1  XDCCMD - Debug TSO CMD processor - will be passed a CPPL
2  XDCCALL - Debug other PGMs in TSO - will be passed an OS PARM field
3  XDCCDF - Debug background jobs or tasks via XDC's Cross Domain Facility

PARAMETERS FOR OPTION 1 OR 2 (FOREGROUND DEBUGGING IN TSO):
Does CMD/PGM use ISPF services? (YES/NO) ==> NO      Dialog APPLID ==>
Should CMD/PGM start APF auth? (YES/NO) ==> NO

CMD/PGM Name  ==> IEFBR14
CMD/PGM Parm  ==>

Tasklib DSNs  ==>
              ==>
              ==>
              ==>
              ==>
              ==>
or DDNAME     ==>
Commands DSN  ==>

PARAMETER FOR OPTION 3 (BACKGROUND DEBUGGING VIA XDC-CDF):
Connect to XDC-CDF using your current TSO Userid? (YES/NO) ==> YES
```

**Figure 19** z/XDC's Startup Panel in ISPF

# **z/XDC® z1.2 INSTALLATION GUIDE**

## **(Installing the Extended Debugging Controller)**

**Go to ISPF's "Command Shell" (option =6) and type XDCLBDEF:**

This will work if you have suitably modified and installed the XDCLBDEF clist. If it does work, then you will see the Startup Panel shown in [Figure 19](#) on page [40](#).

**Go to ISPF's "Command Shell" or to TSO's READY prompt and type: XDCCALL IEFBR14**

This will work if you have installed z/XDC's load libraries (DBCOLE.XDCZ12.XDCLINK and DBCOLE.XDCZ12.XDCPLPA) or load modules into the system's search order for your TSO session.

Doing any of these things should cause the fullscreen display shown in [Figure 20](#) on page [41](#) to appear at your terminal.

```
TCB#9 RB#1 ----- z/XDC ISPF INTERFACE -----
XDC ==>
. DBC854I z/XDC for z/OS (and OS/390)
. DBC855I COPYRIGHT (C) COLE SOFTWARE, LLC - 2001-2003
. DBC856I FOR PRODUCT SUPPORT, PLEASE CALL COLE SOFTWARE AT 540-456-8210

. DBC992I For Online Help, type HELP, then press ENTER. (Not pf-key 1)
. DBC993I Type ? at left of any line for a list of its permitted Line Cmds.
. DBC994I Type LIST HELP to display the Online Help Index.
. DBC996I Type HELP HELP PRINTING for information about printing manuals.

. DBC830I XDC z1.2 ENTERED NONAUTHORIZED, AMODE(24), UNDER RB#3 FROM TCB#9
. DBC891I XDC z1.2 ENTERED AS AN ESTAI OWNED BY TCB#8
. DBC831I THE ERROR LEVEL AND RETRY LEVEL ENVIRONMENTS ARE THE SAME
- DBC841I DEAD MSG: 8067 *** DBC901I SESSION IS READY FOR DEBUGGING, TYPE H AT
  THE LEFT FOR MORE INFORMATION ***

XDC ==> L PSW;L EPSW;L REGS
- PSW 078D1000 00060CE8 (cc-LO) - PRIVATE+5ECE8
- EPSW 078D1000 00060C8A (cc-LO) - PRIVATE+5EC8A
- R0 00009B88 00061F90 E7C4C3C3 C1D3D340 *...h...XDCCALL *
- R4 C9C5C6C2 D9F1F440 80FDA906 0005EE0D *IEFBR14 ..z.....*
- R8 00000000 00010220 0001BBF0 000606E0 *.....0... \*
- R12 0005DE0E 00055E88 80060CEA 00E43000 *.....;h.....U..*
```

**Figure 20** Initial Screen Displayed by z/XDC with Fullscreen Display Support Installed

If, however, you see a display such as that shown in [Figure 21](#) on page [41](#), then most likely z/XDC's various ISPF elements (panels, tables, etc.) have not been properly made available to ISPF. Go back and review the *"Setting Up the XDCPANEL Panel or the XDCLBDEF Clist"* section on page [24](#) for more information. Meanwhile, if you just press the ENTER key, z/XDC will proceed with a normal debugging session but using fullscreen TPUTs (instead of ISPF's Display Services) to paint its displays. The main consequence of this is that you will not be able to use ISPF SPLIT and SWAP commands while using z/XDC.

```
TCB#9 RB#1 ----- z/XDC TPUT INTERFACE -----
XDC ==>
  ISPP100 Panel 'XDCZ12A' error
  ISPP100 PANEL NOT FOUND.

. DBC750I PRESS ENTER TO CONTINUE DEBUGGING USING THE TSO INTERFACE.
```

**Figure 21** Error When z/XDC is Not Properly Installed into ISPF

In any case, once you see the display in [Figure 20](#) on page [41](#), it is verified that z/XDC is installed in the proper system libraries and that it is operational. You may proceed, if you wish, to try out the various z/XDC commands.

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Installing the Extended Debugging Controller)**

When you are done you can terminate z/XDC by pressing PF-key 3 or 4 or by typing "END". This will cause the IEFBR14 program to abend with an 0C1. This is a normal consequence of the END command which (as opposed to the GO command) requests z/XDC to allow the intercepted abend to percolate (i.e. to proceed).

### *Testing Authorized Debugging*

If you have installed the authorized commands XDCCALLA and XDCCMDA, then you should test them now. You may do so as follows:

**Go to z/XDC's Startup Panel, fill it in as shown in [Figure 22](#) on page [42](#), and press ENTER.** (In particular, be sure to respond YES to the question: "Should CMD/PGM start APF auth?") This will work if you have installed z/XDC's Startup Panel into ISPF.

```
----- z/XDC STARTUP PANEL -----
OPTION  ==> 2                                XDC's name ==> XDC
1  XDCCMD - Debug TSO CMD processor - will be passed a CPPL
2  XDCCALL - Debug other PGMs in TSO - will be passed an OS PARM field
3  XDCCDF - Debug background jobs or tasks via XDC's Cross Domain Facility

PARAMETERS FOR OPTION 1 OR 2 (FOREGROUND DEBUGGING IN TSO):
Does CMD/PGM use ISPF services? (YES/NO) ==> NO   Dialog APPLID ==>
Should CMD/PGM start APF auth? (YES/NO) ==> YES

CMD/PGM Name  ==> IEFBR14
CMD/PGM Parm  ==>

Tasklib DSNs  ==>
              ==>
              ==>
              ==>
              ==>
              ==>
or DDNAME     ==>
Commands DSN  ==>

PARAMETER FOR OPTION 3 (BACKGROUND DEBUGGING VIA XDC-CDF):
Connect to XDC-CDF using your current TSO Userid? (YES/NO) ==> YES
```

**Figure 22** Starting z/XDC Authorized from its Startup Panel in ISPF

**Go to ISPF's "Command Shell" or to TSO's READY prompt and type: XDCCALLA IEFBR14**

This will work if you have installed z/XDC's load libraries (DBCOLE.XDCZ12.XDCLINK and DBCOLE.XDCZ12.XDCPLPA) or load modules into the system's search order for your TSO session.

Doing any of these things should cause the fullscreen display shown in [Figure 23](#) on page [43](#) to appear at your terminal. In particular, be sure that message DBC830I reports that z/XDC has been entered **\*AUTHORIZED\***. (If not, then you probably have not correctly updated the IKJTSOxx member of SYS1.PARMLIB. Please see "[XDCCALLA and XDCCMDA: Additional Considerations](#)", on page [20](#), for more information.)

# **z/XDC® z1.2 INSTALLATION GUIDE**

## **(Installing the Extended Debugging Controller)**

```
TCB#6 RB#1 ----- z/XDC TPUT INTERFACE -----
XDC ==>
. DBC854I z/XDC for z/OS (and OS/390)
. DBC855I COPYRIGHT (C) COLE SOFTWARE, LLC - 2001-2003
. DBC856I FOR PRODUCT SUPPORT, PLEASE CALL COLE SOFTWARE AT 540-456-8210

. DBC992I For Online Help, type HELP, then press ENTER. (Not pf-key 1)
. DBC993I Type ? at left of any line for a list of its permitted Line Cmds.
. DBC994I Type LIST HELP to display the Online Help Index.
. DBC996I Type HELP HELP PRINTING for information about printing manuals.

. DBC830I XDC z1.2 ENTERED *AUTHORIZED*, AMODE(24), UNDER RB#3 FROM TCB#6
. DBC891I XDC z1.2 ENTERED AS AN ESTAI OWNED BY TCB#5
. DBC831I THE ERROR LEVEL AND RETRY LEVEL ENVIRONMENTS ARE THE SAME
- DBC841I DEAD MSG: 8067 *** DBC901I SESSION IS READY FOR DEBUGGING, TYPE H AT
  THE LEFT FOR MORE INFORMATION ***

XDC ==> L PSW;L EPSW;L REGS
  PSW 078D1000 00060CE8 (cc-LO) - PRIVATE+5ECE8
- EPSW 078D1000 00060C8A (cc-LO) - PRIVATE+5EC8A
- R0 00009B88 00061F90 E7C4C3C3 C1D3D340 *...h...XDCALL *
- R4 C9C5C6C2 D9F1F440 80FDA906 0005EE0D *IEFBR14 ..z.....*
- R8 00000000 00010220 0001BBF0 000606E0 *.....0... \*
- R12 0005DE0E 00055E88 80060CEA 00E43000 *.....;h.....U..*
```

**Figure 23** Initial Screen Displayed by Authorized Mode z/XDC (with Fullscreen Support Installed)

Also notice that the title bar of the display reports "z/XDC **TPUT** INTERFACE" (not "z/XDC ISPF INTERFACE"). This is an ISPF limitation: ISPF simply does not permit authorized programs to use any of its services, including its Display Services. This means that it will not be possible to use ISPF's SPLIT and SWAP command while debugging authorized programs running in TSO.

Again, you can terminate z/XDC via PF-key 3 or 4 or via an END command.

### **Step 8: Changing the Default MAPLIB Library**

The DBCOLE.XDCZ12.XDCADATA library contains ADATA<sup>31</sup> for a few of z/XDC's load modules, the most important of which is the XDCMAPS load module. XDCMAPS contains mapping information about a very large number of IBM system control blocks. Consequently, it is useful for DBCOLE.XDCZ12.XDCADATA to be setup as the default place for z/XDC to look when it needs to build dsect maps in response to a DMAP command.

In fact, the factory default profile for z/XDC has DBCOLE.XDCZ12.XDCADATA defined as the default library for ADATA searches, but if you've changed the names of the libraries into which you've installed z/XDC, then you will have to go through a process (described below) to make a system-wide change to this default.

z/XDC calls the libraries in which it looks for ADATA "MAPLIB" libraries, and z/XDC has a "SET MAPLIBS" command whereby users can build and save one or more lists of MAPLIB libraries.<sup>32</sup>

z/XDC also has a facility whereby you can create a default MAPLIBS list that will be automatically available to a user's debugging session without requiring him to issue the SET MAPLIBS command. This default MAPLIBS

<sup>31</sup> **ADATA** is a file of data produced during the assembly of a program and that contains a large amount of information about the source code of that program and the assembly process for that program. ADATA can be produced both by IBM's High Level Assembler and by Tachyon Software's Cross Assembler and Dignus' Systems/ASM assembler.

<sup>32</sup> There also is a LIST MAPLIBS ALL command for displaying the current status of both the active MAPLIBS list and all saved MAPLIB lists.

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Installing the Extended Debugging Controller)**

list is kept in the user's session profile. The factory-default default MAPLIBs list names DBCOLE.XDCZ12.XDCADATA as the default MAPLIB library. If you need to change the default MAPLIBs list, then you will have to start up a z/XDC debugging session and then issue the following commands:

```
SET MAPLIBS RESET
SET MAPLIBS libraryname33
SET MAPLIBS SAVE DEFAULT
PROFILE SAVE
```

But don't actually issue these commands yet. Read the next section ("Changing the Default Profile: TFSXDC12") first.

### **Step 9: Changing the Default Profile: TFSXDC12**

TFSXDC12, as mentioned earlier, is a system-wide default profile for z/XDC (see "*Adding XDCMLIB, XDCPLIB, and XDCTLIB*" on page 22). When a user invokes z/XDC **for the first time**, TFSXDC12 is the profile that is loaded for his use.<sup>34</sup> It is loaded by z/XDC regardless of whether z/XDC is running within or outside of an ISPF environment.

If a user changes his profile data and then issues a PROFILE SAVE command, then z/XDC stores the changed profile into the user's own profile library in a member named xxxXDC12, where "xxx" matches z/XDC's name (see "*Renaming z/XDC*" on page 15).

#### *How to Change z/XDC's System Wide Default Profile*

If you wish to change the distributed default profile, then do the following:

- Review the **HELP FULLSCREEN PROFILE** topic in **z/XDC z1.2 User's Guide** (or in z/XDC's Online Help) to learn about the kinds of things that z/XDC saves in session profiles.
- Start up z/XDC. Your current profile will be loaded. (It doesn't matter whether you start z/XDC from within ISPF or from TSO's "READY" mode).
- Type **PROFILE READ XDC TFS** . This will force z/XDC to read the system default profile named TFSXDC12.
- Alternatively, type **PROFILE RESET** to cause z/XDC to reset all profile data to "factory default" values that are assembled directly into z/XDC itself (thereby bypassing TFSXDC12).
- As described in the preceding section ("*Step 8: Changing the Default MAPLIB Library*", page 43) if you need to change z/XDC's default MAPLIB<sup>35</sup> library from its factory default setting of DBCOLE.XDCZ12.XDCADATA to some other name, then you will need to issue the following commands:

```
SET MAPLIBS RESET
SET MAPLIBS libraryname33
SET MAPLIBS SAVE DEFAULT
```

- Now for changing additional profile settings, use z/XDC's **PROFILE** command (without operands) to enter

---

<sup>33</sup>Note, the library name must be given fully qualified and unquoted. So if, for example, your MAPLIB library were named SYS2.XDCZ12.XDCADATA, then you would specify "SET MAPLIBS SYS2.XDCZ12.XDCADATA".

<sup>34</sup>If a user has previously saved his own z/XDC profiles, then z/XDC will not automatically load TFSXDC12. Instead, it will load the user's profile and then automatically convert it, if necessary, to z1.2 format. But z/XDC will not write the converted profile back to disk unless and until the user issues a PROFILE SAVE command.

<sup>35</sup>A **MAPLIB library** is a library that contains ADATA files created by an assembler and from which z/XDC's MAP and DMAP commands can build Source Image Maps for use in Source Level Debugging.

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Installing the Extended Debugging Controller)**

into a menu system (see [Figure 24](#) on page 45) that allows you to display and change all<sup>36</sup> of z/XDC's current profile settings. Make any desired changes by simply overtyping the displayed profile values.

```
TCB#6 RB#1 ----- z/XDC TPUT INTERFACE -----
XDC ==>
  Issue the END, QUIT, or CANCEL command when finished with this panel.

  The currently active profile is named XDC.
  It was read from member TFSXDC12 of DDname ISPTLIB.
  Profile data is saved only upon explicit request.
  Some profiled values have changed since this profile was read.
  Should this profile be saved now? ==> NO

  Select one or more of the following menu options:

  _ Display/Change TSO/ISPF/CDF Related Settings.
  _ Display/Change Terminal Definitions.
  s Display/Change Debugging Session PF-keys.
  _ Display/Change Online Help PF-keys.
  s Display/Change Session Logging Parameters.
  _ Display/Change Window Control Parameters.
  _ Display/Change READ Command and ZAP Command Parameters.
  _ Display/Change FORMAT/TRACE/ZAP/FIND Parameters.
  s Display/Change PRINT and Misc. Other Parameters.
```

**Figure 24** z/XDC's Profile Menu System

- Exit the profile menus via **END** command (PF-key 3) or a **QUIT** command.
- Type **PROFILE SAVE XDC TFS** to save the changed profile back into your profile library under the member named TFSXDC12.
- Leave z/XDC and invoke ISPF's "Move/Copy Utility" (=3.3).
- Move (not just copy) your changed profile (member name TFSXDC12) from your profile library to your system's table library.

### *Which System Wide Default Profile Values You Might Consider Changing*

As discussed above, it is important to set up z/XDC's distributed ADATA library as a default MAPLIB library for use by your user community. If you haven't done so already, then please see "*Changing the Default MAPLIB Library*" on page 43 for more information.

Initially, there should be very few other profile items whose defaults should be changed on a system wide basis. The initial defaults values have received considerable thought, and I feel that they are good for most users. Of course, as users gain experience with z/XDC, they quite likely will want to make specific changes on an individual basis.

In any case, the following default profile settings might be worth changing on a system wide basis:

- **Session Log File Allocation:** z/XDC supports automatic or manual logging of debugging sessions either to disk or SYSOUT spool files. The initial default is for z/XDC to automatically log all debugging sessions to "hold" class X on spool. If "X" is not your standard held output class, then you should change the default to the appropriate class. (See [Figure 25](#) on page 46.)

---

<sup>36</sup>All except MAPLIB lists, that is.

# **z/XDC® z1.2 INSTALLATION GUIDE**

## **(Installing the Extended Debugging Controller)**

```
TCB#6 RB#1 ----- z/XDC TPUT INTERFACE -----
XDC ==>
Issue the END, QUIT, or CANCEL command when finished with this panel.

Currently, the log is open.

SESSION LOGGING OPTIONS:
Automatic session logging in effect? ==> YES
Number of scrollable messages          ==> 10000 (100-32767)
Write log files to disk or spool?     ==> SPOOL (DISK, SPOOL)

Output characteristics when logging to spool:
Dataset SYSOUT class                  ==> X
Place in Held status?                ==> YES
Printer destination                   ==>
Output Limit (OUTLIM)? ==> 0          (0 or 1000-16777215)

Output characteristics when logging to disk:
Unparsed DSNAME                      ==> *P.*XLOG.*D.*T
Resolved DSNAME                      ==> DBCOLE.XDCLOG.D030925.T091511
Allocation volume                    ==>
Allocation unitname                  ==>
Append or overwrite? ==> APPEND      (APPEND, OVERWRITE)
```

**Figure 25** Profile Settings for z/XDC's Session Log

I would not, however, recommend turning off logging since a user cannot predict when he might need it. I also would not recommend rerouting the log from spool to disk because that would lead to an accumulation of disk datasets that someone from time to time would have to go to the trouble of deleting.

A held class on spool is ideal because if it is needed, it can be very easily printed or offloaded to disk, and if it's not needed, then Operations at many computer centers typically runs a periodic command that automatically purges all held output that has remained too long on spool.

- **xxxPRINT File Characteristics:** z/XDC supports a "PRINT" command that users can use to print various things such as selected portions of the Online Help and even entire z/XDC manuals. Users can use the PROFILE Menu System to customize the characteristics of the printed output file. (See [Figure 26](#) on page [46](#).) You may want check out these settings and perhaps change them if necessary to match the characteristics of your most typical printers.

```
TCB#6 RB#1 ----- z/XDC TPUT INTERFACE -----
XDC ==>
Issue the END, QUIT, or CANCEL command when finished with this panel.

PRINT AND MISC. OTHER OPTIONS          CHOICES
60   XDCPRINT lines per page:          10-255 or 0 (no pagination)
X    XDCPRINT and SYSUDUMP output class: A-Z, 0-9, or *
DEFAUL XDCPRINT output status:        HOLD NOHOLD DEFAULT
YES   Upcase csect names and quoted strings? YES NO
NO    Intercept/debug CANCEL/DETACH abends? YES NO
AMODE Meaning of "!" indirect operator: AMODE 64BIT
5    Multitasking timeout interval:    1 to 3600 seconds.
~    Builtin Function Leader Character: ¢ ` ~
```

**Figure 26** Profile Settings for xxxPRINT Output Files

# z/XDC® z1.2 INSTALLATION GUIDE

## (Installing the Extended Debugging Controller)

- **Meaning of the "!" Indirect Operator:** Historically, XDC has used the exclamation point to mean "AMODE sensitive indirect addressing". Now however, with the advent of 64-bit addressing, "!" is the ideal character to mean "64-bit indirect addressing". Unfortunately, that conflicts with z/XDC's history<sup>37</sup>.

To help deal with this conflict, a profiled setting is available by which the user can control how he wants z/XDC to interpret exclamation points. It can be found on the "PRINT and Misc. Other Parameters" page of the Profile menuing System. (See [Figure 26](#) on page 46.)

This setting's factory default is "AMODE" (meaning AMODE sensitive); however, if you're running on a z/OS system (or are planning someday to run on a z/OS system), **I highly recommend that you change this setting from "AMODE" to "64BIT"**.

- **PF-key Arrangements:** z/XDC, like other fullscreen products, supports PF-key definitions. With z/XDC, the PF-key are organized into groups of 12 definitions each, named "SET-A" and "SET-B"<sup>38</sup>. (See [Figure 27](#) on page 47.) The factory default PF-key definitions in SET-A and SET-B differ from each other. Those definitions that are in SET-A are ones that a user is likely to use more frequently than those in SET-B. Accordingly, the SET-A definitions should be assigned to the range of PF-keys that are "easier" to press on the majority of keyboards in use by your user community, while the SET-B definitions should be assigned to those PF-keys that are "less convenient" to press.

```
TCB#6 RB#1 ----- z/XDC TPUT INTERFACE -----
XDC ==>
Issue the END, QUIT, or CANCEL command when finished with this panel.
Terminal Profile Name: *DEFAULT, Selection Mask: Type=***** (in use)

PF-KEY SETS TO RANGES ASSIGNMENTS - Obey the following rules:
- All assignments must be made below in only one column; the other column
  must be left blank.
- Any PF-key set may be assigned to more than one range of codes.
- You do not have to assign sets to all ranges, only to those ranges
  that you need.
- Assign SET-A to the key range that is easiest for you to type.
- In the righthand column below, ranges 11-20 and 13-22 are mutually
  exclusive; you must leave at least one of them blank.

_ Select here to view and update the assigned PF-key sets.

TERMINALS WITH 12 OR 24 PF-KEYS          TERMINALS WITH 10 PF-KEYS
PF-KEY   PF-KEY SETS                    PF-KEY   PF-KEY SETS
RANGES   (A B C)                        RANGES   (A B C)
1-12 ==>  A                               1-10 ==>
13-24 ==> B                               11-20 ==>
25-36 ==>                                13-22 ==>
```

**Figure 27** Profile Settings for Assigning PF-key Sets to PF-key Numbers

z/XDC's "factory defaults" assign the SET-A definitions to PF-keys 1 through 12, and they assign the SET-B definitions to PF-keys 13 through 24. (See [Figure 28](#) on page 48.) This corresponds to the current popularity of PC style "101-key" keyboards which have PF-keys 1-12 positioned conveniently across the top of the board.

<sup>37</sup>For more information see the topic named HELP WHATSNEW Z12 ZARCHITECTURE STORAGE, found either in z/XDC's Release Guide or in the Online Help.

<sup>38</sup>z/XDC also supports a "SET-C" for those terminals that support 36 PF-keys, but I digress.

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Installing the Extended Debugging Controller)**

```
TCB#6 RB#1 ----- z/XDC TPUT INTERFACE -----
XDC ==>
  Issue the END, QUIT, or CANCEL command when finished with this panel.

  _ Select here to view and update the PF-key sets to ranges assignments.

PFK#  SET-A
  1    1ST SET WINDOW DELETE
  2    2ND SPLIT
  3    3RD END
  4    4TH END COMPLETELY
  5    5TH FIND
  6    6TH TSO -
  7    7TH UP -
  8    8TH DOWN -
  9    9TH T
 10   10TH T BY
 11   11TH T NXSEQ(1) NXSEQ(2) NXSEQ(3) NXSEQ(4) NXSEQ(5);GOT
 12   12TH RETRIEVE

          - - -

TCB#6 RB#1 ----- z/XDC TPUT INTERFACE -----
XDC ==>
  Issue the END, QUIT, or CANCEL command when finished with this panel.

  _ Select here to view and update the PF-key sets to ranges assignments.

PFK#  SET-B
 13   1ST SET WINDOW CREATE
 14   2ND SPLIT NEW
 15   3RD END
 16   4TH END COMPLETELY
 17   5TH SCANLOG -
 18   6TH TSO -
 19   7TH UP M
 20   8TH DOWN M
 21   9TH SWAP -
 22  10TH LEFT -
 23  11TH RIGHT -
 24  12TH RETRIEVE +1
```

**Figure 28** Default PF-key Definitions

Note, many older IBM manufactured 327x type terminals had PF-keys clustered at the righthand end of the keyboard with PF-key codes 13-24 assigned to the key tops and codes 1-12 assigned to the key fronts. For those terminals, PF-key codes 13-24 were "easier" to press than codes 1-12.

Accordingly, if your user community largely uses the older style IBM terminals, then you may want to change your local z/XDC installation defaults to assign SET-A to PF-keys 13 through 24 and to assign SET-B to PF-keys 1 through 12. This can be done very easily using z/XDC's Profile Menu system. It also can be done outside of the Profile Menu system using z/XDC's "SET KEYS" command. Note the following:

### **SET KEYS RESET**

Assigns SET-A to keys 1-12 and SET-B to keys 13-24. (This is the factory default.)

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Installing the Extended Debugging Controller)**

### **SET KEYS SWAP**

Also assigns SET-A to keys 1-12 and SET-B to keys 13-24.<sup>39</sup>

### **SET KEYS ASIS**

Assigns SET-A to keys 13-24 and SET-B to keys 1-12.

### **LIST KEYS**

Displays the current key sets assignments.

- **Individual PF-key Assignments:** Many of z/XDC's factory default PF-key assignments are "real nonstandard". (See [Figure 28](#) on page 48.) Accordingly, the temptation, for many people, is high to change them, but **please think twice** before doing so. The factory default definitions have been well thought out. For example, "SET SCREEN CREATE" is a very powerful and useful command, but is relatively hard to type. "HELP", on the other hand, also is powerful and useful, but is relatively easy to type. Accordingly, I have chosen to make "SET SCREEN CREATE" the default setting for PF-key 1, **not** "HELP".

As I said, some of the defaults are real nonstandard, but there are good reasons for this.

Before making any changes to the installation defaults, please read the HELP FULLSCREEN PFKEYS DFLTKEYS topic (in [z/XDC z1.2 User's Guide](#) or in z/XDC's Online Help) for the detailed descriptions of what the default PF-keys are and do.

Refer to the HELP FULLSCREEN PROFILE topic in [z/XDC z1.2 User's Guide](#) or in z/XDC's Online Help for more detailed information about user profiles.

## **Step 10: Installing z/XDC's Cross Domain Facility (CDF)**

z/XDC's "Cross Domain Facility" permits users at fullscreen terminals to debug abends that have occurred in background jobs and system tasks. CDF is implemented as a special service of the z/XDC's fullscreen display option. The communication between a terminal user and a background job is accomplished via VTAM.

In order to use CDF, the computer center must create some VTAM definitions and also run a "life of IPL" task named xxxCDF (where "xxx" matches z/XDC's name, see "[Renaming z/XDC](#)" on page 15). This is a "routing" task that connects interested and permitted users to jobs and tasks that have abended and passed control to z/XDC.

Specifically, the installation of CDF requires the following steps:

- 1.) Member XCDFVTAM of DBCOLE.XDCZ12.XDCCDF contains a series of VTAM statements that define a major node named **XDCCDF** ([Figure 29](#) on page 50). This node is needed by the xxxCDF router task. These statements need to be copied to member xxxCDF of your system's VTAMLST library.

---

<sup>39</sup>In prior versions (X3.0 and older) z/XDC's factory defaults had SET-A assigned to PF-keys 13-24. Hence, the seemingly backwards meanings for the SET KEYS SWAP and SET KEYS ASIS commands.

# *z/XDC® z1.2 INSTALLATION GUIDE*

## **(Installing the Extended Debugging Controller)**

```
XDCCDF  VBUILD TYPE=APPL
XDC      APPL  EAS=1,VPACING=0,AUTH=(ACQ,PASS)
XDCCSIDE APPL  EAS=1,VPACING=0,AUTH=(ACQ)
XDCRTE01 APPL  EAS=1,VPACING=0,AUTH=(ACQ,PASS)
XDCRTE02 APPL  EAS=1,VPACING=0,AUTH=(ACQ,PASS)
...
XDCTFS01 APPL  EAS=1,VPACING=0,AUTH=(ACQ,PASS)
XDCTFS02 APPL  EAS=1,VPACING=0,AUTH=(ACQ,PASS)
...
XDCTSO01 APPL  EAS=1,VPACING=0,AUTH=(ACQ)
XDCTSO02 APPL  EAS=1,VPACING=0,AUTH=(ACQ)
...
```

**Figure 29** Typical VTAMLST File for XDC-CDF

- 2.) Note, XCDFVTAM is good "right out of the box". No changes are necessary. However, if you do want to change the names of the APPLID's defined in XCDFVTAM, then be sure to follow carefully the instructions given in the commentary contained within XCDFVTAM (but not shown in [Figure 29](#)).
- 3.) If you want the xxxCDF node to come up at VTAM startup time, then add xxxCDF's name (where "xxx" matches z/XDC's name) to the list of major node names found in the active ATCCONxxx member of the VTAMLST library. Otherwise, the node will have to be started manually by an operator command ("V NET, ID=xxxCDF, ACT").
- 4.) Member XCDFPARM of DBCOLE.XDCZ12.XDCCDF contains parameters ([Figure 30](#) on page 50) required by the xxxCDF router task. They tell xxxCDF what the names are of the various APPLID's that are defined in XCDFVTAM.

```
VBUILD  XDCCDF
APPLID1 XDC
APPLID2 XDCCSIDE
APPLID3 XDCRTE
APPLID4 XDCTFS
APPLID5 XDCTSO
```

**Figure 30** Typical SYSIN File Parameters for XDC-CDF

These parameters need to be copied to member xxxCDF of a parameter library such as SYS1.PARMLIB. If you have changed the names of the APPLID's in XCDFVTAM, then you will have to make corresponding changes in XCDFPARM so that CDF will know what its APPLID names are. Follow carefully the instructions given in the commentary contained within XCDFPARM.

- 5.) A startup PROC for the xxxCDF router task, such as is shown in [Figure 31](#) on page 51, needs to be added to one of your system's PROCLIB's. The proc's name should be "xxxCDF" (where "xxx" matches z/XDC's name). A model for the PROC can be found in the XCDFPROC member of DBCOLE.XDCZ12.XDCCDF. The JCL should be edited as indicated in [Figure 31](#).

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Installing the Extended Debugging Controller)**

```
//xxxCDF EXEC PGM=xxxTFS, PARM='ROUTER', REGION=0M
//STEPLIB DD DISP=SHR, DSN= <an authorized library containing xxxTFS and xxx>
//SYSIN DD DISP=SHR, FREE=CLOSE, DSN= <a parameter library containing the xxxCDF parms>
//SYSPRINT DD SYSOUT=* (<--- optional DD card)
```

All occurrences of **xxx** should be replaced by z/XDC's name. (See "*Renaming z/XDC*" on page [15](#) for more information.)

The //STEPLIB statement will not be needed, of course, if xxx and xxxTFS are installed into linklist and/or LPA libraries.

**Figure 31** Model JCL for the xxxCDF Router Task

- 6.) The xxxCDF router task needs to have READ access to the XDC.AUTH<sup>40</sup> or AUTH<sup>41</sup> rule.
- 7.) The xxxCDF router task accepts logons from users in much the same way as does TSO or CICS. If your site has a security system, then the xxxCDF router task needs to be defined to that system such that security will permit xxxCDF to make security calls to it in behalf of other users. Please refer back to "*Defining z/XDC to Your Computer's Security System*" on page [29](#) for details.
- 8.) In addition, xxxCDF examines the batch jobs that are pending debugging and issues "RACHECK" type security calls to determine which batch jobs the logged on user is permitted to debug. This check is done before xxxCDF displays to the user the list of jobs pending debugging. This is so that xxxCDF will list only those jobs that the user is permitted to debug. Therefore, if a pending job is not displayed that should be displayed, then this is an indication that the appropriate security system rules are not set up correctly.

The rule that xxxCDF checks is "FASM.---" for CA-ACF2 and CA-Top Secret systems, and "XDC.FASM.---" for RACF systems. Refer back to "*Defining z/XDC to Your Computer's Security System*" on page [29](#) for more information.

- 9.) The following operator commands need to be added to your system's IPL process:

- **V NET, ID=xxxCDF, ACT**

If you have not added xxxCDF's name to the active ATCCONxx member of VTAMLST, then this command needs to be issued during or after VTAM's startup process. It activates the xxxCDF major node definition needed by the xxxCDF task.

- **S xxxCDF**

This command starts the xxxCDF router task. If the xxxCDF task is started before its VTAM node comes up, then xxxCDF will issue operator messages and then just wait for the node.

- 10.) When xxxCDF successfully completes its initialization, it will issue the following two messages and then wait for work to do:

**DBC619I ROUTER MODIFY INTERFACE ACCEPTING COMMANDS.**

**DBC655I ENTER "F xxxCDF,HELP" FOR A LIST OF VALID COMMANDS.**

---

<sup>40</sup>for RACF

<sup>41</sup>for CA-ACF2 or CA-Top Secret

# *z/XDC® z1.2 INSTALLATION GUIDE*

## (Installing the Extended Debugging Controller)

### Step 11: xxxCDF Installation Verification

In order to test xxxCDF, you first must have a background job that has abended and is asking for xxxCDF services. The job shown in [Figure 32](#) on page [52](#) will serve this purpose.

```
//      --- JOB ---  
//IVP      EXEC PGM=xxxIVP  
//STEPLIB DD DISP=SHR,DSN=DBCOLE.XDCZ12.XDCLINK  
//xxxPROF DD DISP=SHR,DSN=<your ISPF profile library> (--- optional DD card)
```

Where xxx matches z/XDC's name. (See "*Renaming z/XDC*" on page [15](#) for more information.)

**Figure 32** Model JCL for Testing xxxCDF

The //xxxPROF DD card, if present, is used by z/XDC to find the user's profile data (member xxxXDC12). From the profile z/XDC determines such things as how long it should wait for a user to log onto the debugging session and whether or not it should display a WTOR to the operators permitting them to abort the logon wait prior to its timing out. If //xxxPROF is omitted, then z/XDC uses "factory defaults".

There are two ways users can log onto CDF:

- TSO users with ISPF can use z/XDC's Startup Panel ("XDCPANEL", see "*Adding XDCMLIB, XDCPLIB, and XDCTLIB*" on page [22](#)). From that panel, select option **3** to connect to xxxCDF.
- Other users can simply logon directly to xxxCDF from an idle VTAM terminal. By default, the necessary command is "LOGON APPLID=xxx"<sup>42, 43</sup>. xxxCDF will then present the user with a screen requesting his userid and TSO password ([Figure 33](#) on page [53](#)).

---

<sup>42</sup>At some Data Centers, the correct command would be "LOGON APPLID(XXX)".

<sup>43</sup>Where "xxx" matches the APPLID1 definition found in the xxxCDF parameter cards. If xxxCDF has been installed as directed, then "xxx" will match z/XDC's name.

# *z/XDC® z1.2 INSTALLATION GUIDE*

## (Installing the Extended Debugging Controller)

```
TCB#23 RB#1 -----XDC-CDF VTAM INTERFACE ----- A.S. XDCCDF
XDC ==>

XX  XX  DDDDDDD  CCCCCC  //  CCCCCC  DDDDDDD  FFFFFFFF
XX  XX  DD  DD  CC  CC  //  CC  CC  DD  DD  FF
XX  XX  DD  DD  CC  CC  //  CC  CC  DD  DD  FF
XXXX  DD  DD  CC  CC  //  CC  CC  DD  DD  FF
XX  DD  DD  CC  CC  //  CC  CC  DD  DD  FFFFFFFF
XXXX  DD  DD  CC  CC  //  CC  CC  DD  DD  FF
XX  XX  DD  DD  CC  CC  //  CC  CC  DD  DD  FF
XX  XX  DD  DD  CC  CC  //  CC  CC  DD  DD  FF
XX  XX  DDDDDDD  CCCCCC  //  CCCCCC  DDDDDDD  FF

USERID          ==>
PASSWORD        ==>
NEW PASSWORD    ==>
RACF GROUP      ==>

PROGRAMMERS NAME      ==>
ACCOUNTING INFORMATION ==>
```

**Figure 33** Logon Screen for VTAM connections to z/XDC's Cross Domain Facility

Once within xxxCDF, the user will be presented with a list of abended background jobs and system tasks that he is permitted (according to system security) to debug ([Figure 34](#) on page 53). The user should merely select the desired job (by typing an **S** next to the job's name). He will then be connected to the job's debugging session. He will see a normal z/XDC debugging screen, and he will be able to issue normal z/XDC commands.

```
TCB#23 RB#1 -----XDC-CDF VTAM INTERFACE ----- A.S. XDCCDF
XDC ==>

Type S below at the left to select the debugging session to connect to.

JOBNAME  STEPNAME  PROCSTEP  PROGRAM  MODULE  ASID  OWNERID
_  CDFXDCTS  A                XDCCALL  WTOR    0015  DBCOLE
```

**Figure 34** XDC-CDF Job Selection menu

For further information, though, the user should type **HELP CDF<sup>44</sup>** before proceeding.

### Step 12: Exit Routines

If you or your users have exit routines that have been written for prior versions or releases of z/XDC, then you probably should reassemble them. There may have been some changes in the programming interface that the exits use. See [z/XDC z1.2 Release Guide](#) for more information. Also, check out the commentary located in the

<sup>44</sup>After selecting the job to be debugged, not before.

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Installing the Extended Debugging Controller)**

#DBCPRM macro (found in the DBCOLE.XDCZ12.XDCMACS library).

z/XDC contains interfaces for an "Installation exit" and for several "User exits". "User exits" generally are provided by the individual users of z/XDC to meet specific needs that may arise during the debugging of specific programs or subsystems. "Installation exits" are more appropriately implemented on a system wide basis.

Only one Installation exit is currently supported by XDC:

- **A System Security Intercept Exit**

This exit can be used to intercept z/XDC's calls to the SAF Interface (the "System Authorization Facility") in z/OS. Whenever z/XDC runs authorized (such as during the XDCINITc PROC, see page 38), it checks the system's PLPA, FLPA, and MLPA for a module named XDCACIF<sup>45</sup>. If found, then a pointer to it is saved in a protected control block for use by both the current as well as all subsequent executions of z/XDC and any of its clones.

XDCACIF must reside on common storage. Any copy of XDCACIF that z/XDC might find in an address space's private area is ignored.

XDCACIF must expect the same inputs and make the same returns as z/OS's SAF Interface does. Refer to IBM documentation for details. The calls that z/XDC makes are documented above in "*Defining z/XDC to Your Computer's Security System*" on page 29. Also, see the HELP EXITS ACIF topic in [z/XDC z1.2 User's Guide](#) or in z/XDC's Online Help.

XDCACIF will intercept only SAF calls made by z/XDC. It will not intercept SAF calls made by any other system, vendor, or user program.

Source code for a sample ACIF exit can be found in DBCOLE.XDCZ12.XDCASM(SRCACIF).

For more information about User Exits, please read the HELP EXITS topic in [z/XDC z1.2 User's Guide](#) or in z/XDC's Online Help. The supported User Exits are:

- **A User Communications Interface ("UCI") Exit**

This exit can be used to replace z/XDC's own user communications interfaces. Normally, z/XDC will communicate with the user via either TPUT/TGET's or WTO/WTOR's. With a UCI exit, user communications can be directed towards any device or path desired. For more information see the HELP EXITS UCI topic in [z/XDC z1.2 User's Guide](#) or in z/XDC's Online Help. Source code for a sample UCI exit can be found in DBCOLE.XDCZ12.XDCASM(SRCONLHG).

- **Consolidated Exits**

z/XDC currently supports the following five consolidated exits:

- **An "Initialization" Exit**

This exit is called every time z/XDC is entered in a non-abortive environment, i.e., whenever z/XDC is called with an SDWA provided. (z/XDC aborts when it is called without an SDWA).

- **A "Resumption" Exit**

This exit is called every time z/XDC is about to return to its caller (usually the RTM, the system's "recovery/termination manager") with "retry" signaled.

- **A "Termination" Exit**

This exit is called every time z/XDC is about to return to its caller with "percolate" signaled.

- **A "User SVC" Exit**

This exit is called by z/XDC when it is processing a TRACE command and the current instruction is a user SVC (or an "EX" of a user SVC). Sometimes, user SVC routines make non-standard returns to locations other than the immediately following instruction. This exit can be used to predict for z/XDC when a user SVC will make such a non-standard return and where that return

---

<sup>45</sup>This module must be named XDCACIF regardless of whether or not z/XDC itself has been renamed.

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Installing the Extended Debugging Controller)**

will be made to. This exit is necessary during z/XDC tracing in order for z/XDC not to lose control of the trace.

- **A "User Commands" Exit**

This exit is called by z/XDC when it has been given a command that it does not recognize. The exit may process or reject the command. Interfaces to several internal z/XDC service routines are made available to the exit. Source code for a sample User Commands Exit can be found in `DBCOLE.XDCZ12.XDCASM(SRCXUCMD)`. (SRCXUCMD implements a LIST TIOT command for z/XDC.)

All consolidated exits must be packaged together into a single module and front-ended by a user written router routine. Thus, if any consolidated exit is written, then at least null versions of all consolidated exits must be written. Use of consolidated exits is documented in the HELP EXITS MISXITS topic in **z/XDC z1.2 User's Guide** or in z/XDC's Online Help. Source for a sample router module can be found in `DBCOLE.XDCZ12.XDCASM(SRCXITSR)`.

- **A "Front-end/Back-end" Routine**

Every time z/XDC receives control, it GETMAIN's and builds an multi-page temporary data area. Every time it releases control, it FREEMAIN's that area. z/XDC has support that allows a front-end routine to provide the pages of storage that z/XDC uses for its temporary data. This has been useful for making z/XDC operate in certain highly constrained environments found at one or two customer sites. Please see the HELP EXITS topic in **z/XDC z1.2 User's Guide** or in z/XDC's Online Help for more information.

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **INSTALLING A DEBUGGING INTERFACE INTO JES2**

DBCOLE.XDCZ12.XDCJES2 contains an interface for using z/XDC to debug JES2 code. This interface will fit all releases of JES2 from MVS/370 SP 1.3.6 through at least the z/OS 1.3 release of JES2 (and probably beyond).

Please understand that this interface is necessary only if you intend to use z/XDC to debug JES2 code and JES2 exit routines. If you do not intend to write any mods or exits for JES2, then you need not install this interface, and you can skip reading this section.

If you decide to install this interface, then you should also make a copy of this section of this manual available to your JES2 programmers. It contains information that they will need to know. Also they should read the HELP DEBUGGING JES2 topic in z/XDC z1.2 User's Guide or in z/XDC's Online Help.

### **What the XDC/JES2 Interface Is and Does**

The XDC/JES2 interface allows the customer to use z/XDC to debug mods and exit routines running under JES2's main task.<sup>46</sup> This interface consists of three components: two JES2 exits and an optional source code update file. The two exits are an Exit 0 for implementing an "XDC" initialization option and an Exit 5 for implementing a "\$XDC" command. The source code modification makes changes to JES2's "\$CB" and "\$MODULE" macros in support of z/XDC's csect mapping command.

**Each of the three components of the XDC/JES2 interface is completely independent of the other two. A customer may freely install or not install any or all of the components in any combination.**

### **The Members of DBCOLE.XDCZ12.XDCJES2**

The XDCJES2 library contains the following members for the JES2 interface:

#### **J2IFXIT0 and J2IFXIT5**

Contains source code for a JES2 Exit 0 and an Exit 5 routine, respectively.

#### **J2IFASM0 and J2IFASM5**

Contains sample JCL for assembling J2IFXIT0 and J2IFXIT5, respectively.

#### **J2IFLKD0 and J2IFLKD5**

Contains sample JCL for linkediting J2IFXIT0 and J2IFXIT5, respectively. Please note that these two exits must be linkedited as "serially reusable" (i.e. "PARM='REUS...") and not as reentrant.

#### **J2IFUPDT**

Contains a source code update to JES2's \$CB and the \$MODULE macros.

#### **J2IFUJCL**

Contains sample JCL for applying J2IFUPDT to JES2's source library.

#### **J2IFHASM**

Contains sample JCL (a) for creating a HASPDOC load module containing a full set of JES2 control block maps for use by z/XDC, and (b) for reassembling any or all of JES2's source modules with csect maps for use by z/XDC and with redundant dsect maps edited out.

---

<sup>46</sup>Currently, the interface does not directly support debugging exits running under JES2 subtasks. To debug such exits, follow the procedures outlined in z/XDC's Online Help. Start z/XDC and then type HELP DEBUGGING EXITROUTINES.

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Installing a Debugging Interface into JES2)**

### **Exit 0: The "XDC" Initialization Option**

Exit 0 adds support permitting a system operator to include "XDC" in his reply to JES2's initialization WTOR ("\$HASP426 SPECIFY OPTIONS - JES2 SP v.r.m"). If the operator does specify "XDC", then an exit routine will locate and load into storage a copy of z/XDC, issue an ESTAE macro to make z/XDC the newest ESTAE routine, and then execute a #DIE macro to breakpoint to z/XDC. At this point a JES2 programmer can use z/XDC's commands to load maps, set breakpoints, etc. Then when he is ready, he can issue z/XDC's "GO" command to return control back to JES2 which will then proceed with its initialization.

This "XDC" initialization option can be used by the JES2 programmer to turn the z/XDC debugging interface on and to pass control to z/XDC as early as possible in JES2 initialization. From this point z/XDC commands can be used to set breakpoints for the debugging of JES2 initialization routines as well as any other JES2 main task routines.

Due to JES2 environment limitations existing at the time that JES2 searches for and invokes Exit 0 routines, the load module containing z/XDC's Exit 0 must be named exactly "HASPXIT0". If the customer already has another Exit 0 routine, then that routine must be merged with z/XDC's Exit 0. For more information, please refer to the appropriate **User Modifications and Macros** manual for your release of JES2. Also, refer to commentary located within the source code for z/XDC's Exit 0.

The source code for z/XDC's Exit 0 is contained in "J2IFXIT0". Sample JCL for assembling the exit is contained in "J2IFASMO". Sample JCL for linking the exit is contained within "J2IFLKD0". Please note that this exit must be linked as "serially reusable" (i.e. "PARM='REUS...") and not as reentrant. Also, it is recommended that this exit be assembled and linked with PARM=TEST.

JES2 initialization parameter cards are not needed for defining EXIT 0. This is because JES2 searches for and invokes Exit 0 routines long before it processes its initialization parameter cards.

For additional technical information, please see commentary found within the source code located in J2IFXIT0.

### **Exit 5: The "\$XDC" Command**

Exit 5 adds support for a "\$XDC" command and makes a change to the handling of the "\$PJES2,ABEND" command.

The "\$XDC" command can be used to turn on, turn off, and query the status of z/XDC debugging within JES2 as follows:

#### **"\$XDC ON" or just "\$XDC"**

This command turns on z/XDC debugging within JES2's main task. First, it checks to see if z/XDC has already been loaded into storage and established as the JES2 main task's newest ESTAE routine. If not, then it loads a copy of z/XDC into storage and then issues an "ESTAE" macro to make it the newest ESTAE routine.

Next, the command attaches a subtask that traps to z/XDC via a #DIE macro (available from DBCOLE.XDCZ12.XDCMACS) to pass control to z/XDC. At this point, z/XDC commands can be used to load maps, set breakpoints, etc. When a GO command is issued, the subtask terminates until the next \$XDC ON command is issued.

#### **"\$XDC OFF"**

This command turns z/XDC debugging off in JES2. If z/XDC currently is the newest ESTAE routine, then this command issues an "ESTAE 0" macro to cancel z/XDC and then a "DELETE" macro to remove z/XDC from the address space.

#### **"\$XDC STATUS" or "\$XDC ?"**

This command displays messages reporting the current status (on or off) of the z/XDC interface.

No ill effects arise from issuing multiple "\$XDC ON"s and/or "\$XDC OFF"s in a row. "\$XDC ON" will always

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Installing a Debugging Interface into JES2)**

breakpoint to z/XDC, but it will not create excessive z/XDC ESTAE's. "\$XDC OFF" will delete the newest ESTAE only if it is z/XDC.

When the z/XDC interface is on, any abends, \$ERRORs, and/or breakpoints that occur within JES2's main task<sup>47</sup> will cause control to pass to z/XDC. On the other hand, when the interface is off, all abends, \$ERRORs, and breakpoints will cause control to be passed directly to JES2's "Catastrophic Error" routine, "\$ABEND" (which will see breakpoints as nothing more than 0C1 abends).

The source code for z/XDC's Exit 5 is contained in "J2IFXIT5". Sample JCL for assembling the exit is contained in "J2IFASM5". Sample JCL for linking the exit is contained within "J2IFLKD5". Please note that this exit must be linked as "serially reusable" (i.e. "PARM='REUS...") and not as reentrant. Also, it is recommended that this exit be assembled and linked with PARM=TEST.

To activate z/XDC's Exit 5, the following parameter cards need to be added to JES2's "HASPPARM" file:

```
LOADMOD (XDCEXIT5)
EXIT5 ROUTINE (EXIT5XDC)
```

For additional technical information, please see commentary found within the source code located in J2IFXIT5.

### **Exit 5: The "\$PJES2,ABEND" Command**

When z/XDC's interface is on, all abends, including \$ERROR abends, occurring within JES2's main task are intercepted and handled by z/XDC instead of by JES2's own routines. This includes the "PJ2" \$ERROR that occurs when the "\$PJES2,ABEND" command is issued.

When z/XDC intercepts and handles an abend (such as the one created by the "\$PJES2,ABEND" command), it is possible that the JES2 programmer might issue z/XDC's "GO" command to cause JES2 to resume execution as if the abend had never happened. JES2's own implementation of the "\$PJES2,ABEND" command, however, does not anticipate this possibility, and so it has no way to return control to JES2's dispatcher to resume normal processing.

The implementation of the "\$PJES2,ABEND" command within z/XDC's Exit 5 provides the following way to resume normal JES2 execution, should the JES2 programmer so desire:

- When z/XDC gains control as a result of a \$PJES2,ABEND command, issue a "MAP XDCEXIT5+0" command to load both a linkedit map and a csect map for z/XDC's Exit 5 routine.
- Issue a "S Q XDCEXIT5" to make Exit 5 the default load module and csect.
- Issue "GO .PJ2RESUM" to pass control from z/XDC back to JES2.

The "\$PJES2,ABEND" command is the only form of the \$PJES2 command that is handled by z/XDC's Exit 5. All other forms of the \$PJES2 command are handled by JES2's own routines.

### **Debugging JES2 with z/XDC Clones**

By default the z/XDC interface implemented via the above described Exit 0 and Exit 5 will load and use a load module named "XDC". However, z/XDC contains extensive support permitting it to be renamed to any other 3-character name. When this is done, the renamed z/XDC is referred to as a "clone" of z/XDC. See "*Renaming z/XDC*" on page [15](#) for more information.

If you need to have the XDC/JES2 interface look for and use a z/XDC clone, then you must add the following

---

<sup>47</sup>Currently, the interface does not directly support debugging exits running under JES2 subtasks. To debug such exits, follow the procedures outlined in z/XDC's Online Help. Start z/XDC and then type HELP DEBUGGING EXITS.

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Installing a Debugging Interface into JES2)**

DD card to JES2's startup JCL:

```
//XDCISxxx DD DUMMY
```

where "xxx" is replaced by the z/XDC clone's name. For example, if z/XDC has been renamed at your shop to "Z12", then you will need to add:

```
//XDCISZ12 DD DUMMY
```

to JES2's startup JCL.

The presence of a "//XDCISxxx" DD card in JES2's startup JCL will have the following effects of z/XDC's interface:

- Both Exit 0 and Exit 5 will look for and load "xxx" instead of "XDC".
- Exit 0 will change the name of the z/XDC initialization option from "XDC" to "xxx".
- Exit 5 will change the name of the \$XDC command from "\$XDC" to "\$xxx".

It is the JES2 programmer's responsibility to choose a clone name that does not interfere with other JES2 initialization options and operator commands.

### **Communicating with the XDC/JES2 Interface**

When running in a non-TSO address space, z/XDC has available to it two possible mechanisms for communicating with a debugging programmer: linemode style WTO/WTOR's to a selected operator's console, or fullscreen TPUT/TGET's via z/XDC's "Cross Domain Facility" ("CDF") to a VTAM or TSO terminal. z/XDC can be setup to use either mechanism in JES2 regardless of whether the JES2 being debugged is a primary or a secondary JES2.

The linemode style WTO/WTOR interface is a fallback method of communication. The preferable method is the fullscreen interface via the Cross Domain Facility. In order to use CDF, however, all of the following conditions must be met:

- z/XDC's CDF component must be licensed and installed to run at your site.
- The "xxxCDF" router task must be running (where "xxx" is either "XDC" or the name of the z/XDC clone being used). Note, one implication of this is that it is not possible to use fullscreen communications when debugging JES2 initialization routines in the primary JES2, since at that point in time it will not yet have been possible to start xxxCDF.
- A "//xxxWTOR DD DUMMY" card must **NOT** be included in JES2's startup JCL. (This would tell z/XDC to communicate via WTO/WTORs instead of via CDF.)
- An "//xxxPROF" DD card also should be included that points to a card-image library that contains a copy of the JES2 programmer's "xxxXDC12" member from his own ISPF profile library. This contains the PF-key, screen layout, and other definitions needed by xxxCDF for the fullscreen support.

For more information concerning the Cross Domain Facility, please refer to z/XDC's Online Help. (Start z/XDC and then type "HELP CDF".)

### **J2IFUPDT: JES2 Csect Mapping Support**

J2IFUPDT contains an IEBUPDTE format update file that contains certain source code modifications to JES2's \$CB and \$MODULE macros. This source code update is optional. It is provided to facilitate the process of making

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Installing a Debugging Interface into JES2)**

JES2 csect maps available for use by z/XDC during JES2 browsing or debugging. This update should be applied only if you are making source code mods to JES2. If you are just writing JES2 exit routines, then there is no reason to apply this update.

This update file correctly fit all versions and releases of JES2 from MVS/370 SP 1.3.6 through at least MVS/ESA SP 4.3.0 (and probably beyond).

These updates to the \$CB and \$MODULE macros cause the JES2 control blocks portion of all assemblies (except the HASPDO assembly) to be bracketed with "SYMDEL" and "SYMNODEL" dsect cards. The presence of the SYMDEL and SYMNODEL dsect cards has no effect whatsoever on JES2 object code. This update does not in any way affect JES2's logic or behavior. Therefore, no production facility can ever become dependent on this update.

However, if the JES2 code is assembled with "PARM='TEST ...'", then the names "SYMDEL" and "SYMNODEL" will appear in the object deck symbol table (card type "SYM") that is generated by the Assembler. If, prior to linkedit, the object deck is then run through a post processing utility named "XDCSYMED", then all symbols occurring between the SYMDEL and SYMNODEL names will be purged from the object deck. This reduces the size of each object deck by hundreds of cards, and eventually when you linkedit the object decks together (using "PARM='TEST ...'" on the linkedit) to build the various JES2 load modules, their on-disk sizes will be reduced by literally thousands of card images (as compared to not using XDCSYMED and the SYMDEL/SYMNODEL dsect cards). See z/XDC's Online Help for more information about using "XDCSYMED". (Start z/XDC and then type "HELP MAPS XDCSYMED".)

Note, this process for eliminating excess symbol table entries is necessary because the Binder itself does nothing whatsoever to recognize and eliminate redundant "SYM" cards and entries.

The size and logic of load modules read into storage are never affected by the presence or absence of "SYM" records. This is because the system's program fetch routine ("IEWFETCH") always ignores SYM records.

The updates to \$CB and \$MODULE are contained in "J2IFUPDT". Sample JCL for applying the update is contained in "J2IFUJCL". Sample JCL for assembling and then symbol editing JES2 modules is contained in J2IFHASM.

## **Using JES2 Csect Maps**

You may or may not decided that you want to have csect maps available to z/XDC during JES2 debugging. If you are just writing JES2 exit routines, then you probably will not need JES2 csect maps. On the other hand, if you are writing mods to JES2 source code, then csect maps will be very useful to you.

If you do wish to use csect maps, then you might decide to generate them for either all or only a few JES2 source modules. To generate csect maps, you must do the following:

- First, you must apply the update found in J2IFUPDT to JES2's source library, SYS1.HASPSRC.
- Then you must assemble the desired one, several, or all JES2 source modules with PARM=TEST specified. Then you will have to linkedit the affected JES2 load modules also with PARM=TEST specified.
- You must assemble and linkedit the desired JES2 modules outside of SMP/E. This is because SMP/E does not support PARM=TEST.
- In order to reduce the on-disk size of the JES2 object and load libraries by many many cylinders, you will have to append to your assembly JCL a second step to use the XDCSYMED utility to remove excess SYM table entries from the object decks. This is because most or all of the JES2 source modules assemble approximately the same very large set of control block macros, and this leads to huge amounts of redundant information in the object modules. Worse, when the Binder combines the object modules into load modules, it takes no steps whatsoever to identify and remove redundant SYM table entries. It merely propagates them wholesale into the load module.

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Installing a Debugging Interface into JES2)**

- In order to make XDCSYMED operate effectively, pairs of "SYMDEL/SYMNODEL" DSECT cards have to be added to the JES2 source modules to delimit for XDCSYMED those SYM table entries that are to be removed from the object decks. This is what the J2IFUPDT update does to the \$CB and \$MODULE macros.

J2IFHASM Contains sample JCL for reassembling all of JES2's source modules with PARM=TEST specified and with XDCSYMED invoked to edit the object modules. This leads to the creation of JES2 object and load modules with csect maps available for use by z/XDC and with redundant dsect maps edited out.

### **Using JES2 Dsect Maps**

The generation of dsect maps for JES2 control blocks is a separate and somewhat simpler process than generating csect maps. All you have to do is assemble and linkedit HASPDOC with PARM=TEST specified. This creates a load module that contains a full set of JES2 control block maps in a form usable by z/XDC. Doing this assembly and linkedit will in no way affect JES2 processing. In fact JES2 will never load, make use of, or even know of the existence of the HASPDOC load module. However, when you use z/XDC to browse or debug JES2, you will find the control block maps provided by HASPDOC to be immensely useful in identifying and referencing the many control structures found within the JES2 address space.

J2IFHASM contains sample JCL for creating a HASPDOC load module containing a full set of JES2 control block maps for use by z/XDC. Note that when creating the HASPDOC load module, it is not necessary (although it doesn't hurt) to apply the J2IFUPDT updates against the \$CB and \$MODULE macros. It also is not necessary (but again, it doesn't hurt) to process the HASPDOC object deck through the XDCSYMED utility.

### **Browsing JES2 via Foreign Address Space Mode**

The XDC/JES2 interface described above is "invasive"; i.e., when used it can interrupt JES2 main task processing: printers stop, remotes time out, internal and other readers lock up, TSO logons also lock up, etc. This interface can be extremely useful during program development, and it can certainly be used freely against a secondary, non-production JES2 or on a private "sandbox" system. It is not, however, appropriate for use on a production system.

If all you want to do is to browse JES2's address space without affecting its processing, z/XDC's "Foreign Address Space Mode" is an excellent tool to use. All you need to do is:

- Logon to your TSO terminal,
- Invoke an authorized z/XDC debugging session ("XDCCALLA IEFBR14"),
- Delete z/XDC's lower display screen (move the cursor down and press PF-key 13),
- Issue "SET ASID JES2".

At this point you are connected to JES2's address space, and you can use z/XDC's DISPLAY, FORMAT, LIST, EQUATE, MAP, DMAP, USING, and ZAP commands to display, map, format, and even sometimes repair all structures in JES2's private storage.

### **A Browsing Example**

As an example, try the following command sequence:

<code>XDCCALLA IEFBR14</code>	Starts up an authorized debugging session.
<code>SET ASID JES2</code>	Switches to Foreign Address Space Mode against the JES2 address space.
<code>LIST TASKS</code>	Displays JES2's current subtask structure. Also (re)creates "TCB#n"

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Installing a Debugging Interface into JES2)**

	equates.
LIST RBS TCB#3	Displays the RB's (usually just one) currently queued to JES2's main task. Also (re)creates "RB#n" equates.
LIST REGS RB#1	Displays the current registers being used (at least for the then current few nanoseconds) by the oldest RB running under JES2's main task.
LIST PSW RB#1	Ditto for the PSW.
D HASJES20.X#1	Displays JES2's HCT, unformatted.
DMAP HASPDOC.HCT	Loads a map of the HCT.
USING HCT +0	Bases the HCT map on top of the actual HCT.
F +0,500	Formats and displays lots of the HCT.
EQ JOBQ . \$JOBQPTR?	Marks the start of JES2's job queue.
DMAP .JQE	Loads a JQE map.
FIND 'MYJOBID' JOBQ	Locates a JQE of interest.
USING .JQEJNAME +0	Bases the JQE map, properly aligned, onto the actual JQE.
F JQE 50	Formats a portion of the JQE map.
.	
.	
.	
etc.	

# ***z/XDC® z1.2 INSTALLATION GUIDE***

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **APPENDIX A: CHANGE HISTORY - z/XDC RELEASE z1.2**

z/XDC's Change History is no longer maintained in this manual. It has been moved to z/XDC's Online Help. To see what's new with this release, start a z/XDC debugging session<sup>48</sup>, then type "HELP WHATSNEW".

---

<sup>48</sup>The easiest way to start a "token" z/XDC debugging session is to type "XDCCALL IEFBR14" at ISPF's "TSO Command Processor" panel (option =6).

# ***z/XDC® z1.2 INSTALLATION GUIDE***

# *z/XDC® z1.2 INSTALLATION GUIDE*

## INDEX

Please note that this index is sorted according to the ASCII collating sequence, not EBCDIC. In particular, this means that digits sort in front of (not behind) alphabets, and that only some special characters sort in front of alphabets. Others sort behind alphabets.

The word processing program that is used here supports only two levels of index entries: main topics and sub-topics. When a sub-topic entry says "see major topics", this indicates that you should look for the same index entry among the main topics.

access control	
ACF2 (see ACF2)"	<a href="#">33</a>
AUTH resource (see XDC.AUTH resource)8	<a href="#">30</a>
CDF	<a href="#">30</a>
FASM resource (see XDC.FASM resource)8	<a href="#">30</a>
foreign address spaces)	<a href="#">29, 30</a>
GZAP resource (see XDC.ZAP resource)7	<a href="#">30</a>
privileged mode"	<a href="#">29, 30</a>
RACF (see RACF)"	<a href="#">31</a>
SAF, use of	<a href="#">30</a>
TOP SECRET (see TOP SECRET).	<a href="#">35</a>
unprotected	<a href="#">30</a>
XDC.AUTH resource\$	<a href="#">30</a>
XDC.FASM resource\$	<a href="#">30</a>
XDC.ZAP resource#	<a href="#">30</a>
ZAP resource (see XDC.ZAP resource)6	<a href="#">30</a>
zapping	<a href="#">30</a>
ACF2	<a href="#">33</a>
ACF2SAMP	<a href="#">35</a>
OPTS record	<a href="#">34</a>
refresh	<a href="#">34</a>
RESDIR record	<a href="#">34, 35</a>
resource rules	<a href="#">35</a>
SAFMAPS record	<a href="#">34</a>
SAFPROT record	<a href="#">34</a>
ADATA	
MAPLIBs	<a href="#">43</a>
Address spaces	
access to (see access control)1	<a href="#">29</a>
APPLY CHECK	
Don't even try it!"	<a href="#">14</a>
APPLY REDO	
Don't even try it!!	<a href="#">15</a>
AUTH resource (see XDC.AUTH resource)	
*	<a href="#">30</a>
AUTHCMD	<a href="#">20</a>
Authorization	
XDCCALLA and XDCCMDA&	<a href="#">20</a>
Authorized mode (see privileged mode debugging)	
4	<a href="#">29</a>
BDT (see Bulk Data Transfer)	
!	<a href="#">20</a>
BDT warning	<a href="#">20</a>
Bulk Data Transfer	
copying XDCHELPM'	<a href="#">20</a>
Bulk Data Transfer (see BDT)	
!	<a href="#">20</a>
CA-Top Secret	<a href="#">35</a>
maintenance requirements*	<a href="#">37</a>
catalog, master	<a href="#">10, 18, 19</a>

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Index)**

CDF	
access control	<u>30</u>
installing	<u>49</u>
IVP	<u>52</u>
Change history	<u>64</u>
Class Descriptor Table (RACF)	
"	<u>31</u>
clist	
XDCLBDEF	<u>23</u>
clists	
RECFM conversion	<u>22</u>
XDCCLIST	<u>21</u> , <u>23</u>
XDCLBDEF	<u>22</u> , <u>24</u>
CLPA	<u>26</u>
commands	
LICENSE	<u>29</u>
LIST MAPLIBS	<u>43</u>
SET MAPLIBS	<u>43</u>
Commands Reference manual	<u>2</u>
COMMNDxx	<u>38</u>
Compatibility	
with prior XDC's"	<u>7</u> , <u>15</u>
copying XDCHELPM	<u>15</u> , <u>20</u>
Bulk Data Transfer'	<u>20</u>
CSI dataset	<u>12</u>
datasets	
DBCOLE.XDCZ12.INSTALL.XMITLIB.TERSED1	<u>3</u>
DBCOLE.XDCZ12.INSTALL.XMITLIB*	<u>3</u> , <u>4</u>
DBCOLE.XDCZ12.XDCADATA#	<u>43</u>
dlib zone	<u>12</u>
SMP, creating	<u>12</u>
SYS1.PARMLIB	<u>17</u>
SYS3.XDC.CSI	<u>12</u>
SYS3.XDC.SMPLOG	<u>12</u>
SYS3.XDC.SMPMTS	<u>12</u>
SYS3.XDC.SMPPTS	<u>12</u>
SYS3.XDC.SMPSCDS	<u>12</u>
SYS3.XDC.SMPSTS	<u>12</u>
SYS3.XDCX31.name (see "name")*	<u>13</u>
target zone	<u>12</u>
unterse.jcl	<u>3</u>
XDCACF2	<u>13</u>
XDCASM	<u>13</u>
XDCCDF	<u>13</u>
XDCCLIST	<u>13</u> , <u>21</u>
XDCCMDS	<u>13</u> , <u>26</u>
XDCDLNK	<u>13</u>
XDCDSRC	<u>13</u>
XDCJCL	<u>13</u>
XDCJES2	<u>13</u>
XDCLINK	<u>13</u> , <u>18</u>
XDCMACS	<u>13</u>
XDCMLIB	<u>13</u> , <u>22</u>
XDCPLIB	<u>13</u> , <u>22</u>
XDCPLPA	<u>13</u> , <u>18</u>
XDCTLIB	<u>13</u> , <u>22</u>
xdcz12.zip	<u>1</u>
xmitlib.trs	<u>2</u> , <u>3</u>
DBC514I message	
System Interface Initialization Report:	<u>39</u>

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Index)**

DBCOLE.XDCZ12.INSTALL.XMITLIB dataset	
* .....	<a href="#">3, 4</a>
DBCOLE.XDCZ12.INSTALL.XMITLIB.TERSED dataset	
1 .....	<a href="#">3</a>
DBCOLE.XDCZ12.XDCADATA dataset	
# .....	<a href="#">43</a>
distribution package .....	<a href="#">1</a>
e-mail (see internet) .....	<a href="#">ii</a>
FACILITY class .....	<a href="#">31</a>
FASM resource (see XDC.FASM resource)	
* .....	<a href="#">30</a>
Foreign address spaces	
access to (see access control)9 .....	<a href="#">29</a>
FTP address (see internet) .....	<a href="#">ii</a>
generalized resource rules	
ACF2# .....	<a href="#">35</a>
GZAP resource (see XDC.ZAP resource)	
) .....	<a href="#">30</a>
History of changes .....	<a href="#">64</a>
home page (see internet) .....	<a href="#">ii</a>
IEASYSxx	
LNKAUTH=LNKLST .....	<a href="#">19</a>
IKJTSOxx	
AUTHCMD .....	<a href="#">20</a>
INSTALIB	
editing .....	<a href="#">11</a>
Installation steps .....	<a href="#">7</a>
Post-SMP/E Phase' .....	<a href="#">8, 15</a>
Pre-SMP/E Phase& .....	<a href="#">8, 9</a>
SMP/E Phase" .....	<a href="#">8, 13</a>
internet	
e-mail address .....	<a href="#">ii</a>
FTP address .....	<a href="#">ii</a>
home page .....	<a href="#">ii, iii</a>
web address .....	<a href="#">ii</a>
IPL .....	<a href="#">26</a>
ISPF	
XDCPANEL panel .....	<a href="#">24</a>
ISPF messages	
XDCM00 .....	<a href="#">23</a>
ISPF panel	
XDCPANEL .....	<a href="#">23</a>
XDCPHELP .....	<a href="#">23</a>
XDCPHLPx .....	<a href="#">23</a>
XDCT31A .....	<a href="#">23</a>
ISPF panels	
XDCPANEL .....	<a href="#">24</a>
XDCT31B .....	<a href="#">23</a>
ISPF table	
TFSPROF .....	<a href="#">23</a>
ISPF tables	
TFSXDC31 .....	<a href="#">23</a>
IVP	
for CDF .....	<a href="#">52</a>
in TSO .....	<a href="#">40</a>
jobs	
SMPBASE .....	<a href="#">12, 14</a>
SMPCSI .....	<a href="#">11, 12</a>
SMPDDDEF .....	<a href="#">11, 12</a>
SMPMAINT .....	<a href="#">12, 14</a>

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Index)**

Key 0 (see privileged mode debugging)	
* .....	<u>29</u>
legal statements	
trademark notice%	<u>iii</u>
usage warning"	<u>ii</u>
libraries (see datasets)	<u>16</u>
license activation	<u>26</u>
LICENSE command	<u>29</u>
LIST MAPLIBS command	<u>43</u>
LLA refresh	<u>19</u>
LNKAUTH=LNKLST	<u>19</u>
LNKLSTxx	<u>19</u>
load modules	
XDCMAPS	<u>43</u>
LPALSTxx	<u>18</u>
maintenance	
cumulative packaging\$	<u>10</u>
discard older packages&	<u>10</u>
MAPLIBs	
ADATA	<u>43</u>
changing the default	<u>43</u>
DECOLE.XDCZ12.XDCADATA"	<u>43</u>
default	<u>43</u>
master catalog	<u>10, 18, 19</u>
messages	
DBC514I	<u>39</u>
Messages Reference manual	<u>2</u>
naming conventions	<u>10</u>
OPTS record	<u>34</u>
panels (see ISPF panels)	<u>23</u>
PDS, a public domain command	
!	<u>16</u>
Post-SMP/E Phase	<u>8, 15</u>
Pre-SMP/E Phase	<u>8, 9</u>
profile	
how to change	<u>44</u>
what to change	<u>45</u>
PROGxx	<u>19</u>
Quick Reference manual	<u>2</u>
RACF	<u>31</u>
Class Descriptor Table	<u>31</u>
CLASSACT	<u>32</u>
FACILITY class	<u>31</u>
GENERIC	<u>32</u>
RACLIST	<u>32</u>
Re-IPL	<u>26</u>
Release Guide manual	<u>2</u>
Renaming XDC	<u>15</u>
renaming XDCCALL	<u>16</u>
RESDIR record	<u>34, 35</u>
resource rules	
ACF2	<u>35</u>
SAF, use of	<u>30</u>
SAFMAPS record	<u>34</u>
SAFPROT record	<u>34</u>
security (see access control)	
"	<u>29</u>
Service SVC (see SVC, XDC's)	
!	<u>38</u>
SET MAPLIBS command	<u>43</u>

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Index)**

slib datasets	
creating	<a href="#">12</a>
SMP datasets	
creating	<a href="#">12</a>
SMP/E Phase	<a href="#">8</a> , <a href="#">13</a>
SMPBASE job	<a href="#">12</a> , <a href="#">14</a>
SMPCSI job	<a href="#">11</a> , <a href="#">12</a>
SMPDDDEF job	<a href="#">11</a> , <a href="#">12</a>
SMPLOG dataset	<a href="#">12</a>
SMPMAINT job	<a href="#">12</a> , <a href="#">14</a>
SMPMTS dataset	<a href="#">12</a>
SMPPTS dataset	<a href="#">12</a>
SMPSCDS dataset	<a href="#">12</a>
SMPSTS dataset	<a href="#">12</a>
Supervisor state and key (see privileged mode debugging)	
=	<a href="#">29</a>
SVC, XDC's	
installing	<a href="#">38</a> , <a href="#">39</a>
integrity	<a href="#">38</a>
when not installed!	<a href="#">39</a>
SYS1.PARMLIB	
COMMNDxx	<a href="#">38</a>
IKJTSOxx	<a href="#">20</a>
SYS1.PARMLIB dataset	<a href="#">17</a>
IEASYSxx!	<a href="#">19</a>
IKJTSOxx!	<a href="#">20</a>
LNKLSTxx!	<a href="#">19</a>
LPALSTxx!	<a href="#">18</a>
PROGxx	<a href="#">19</a>
SYS3 datasets (see datasets)	
!	<a href="#">12</a>
System Authorization Facility (see SAF)	
,	<a href="#">30</a>
System Interface Initialization Report	
DBC514I message:	<a href="#">39</a>
tables (see ISPF tables)	<a href="#">23</a>
target datasets	
creating	<a href="#">12</a>
target libraries	
XDC31	<a href="#">17</a>
XDCCALL	<a href="#">17</a>
XDCCALLA	<a href="#">17</a>
XDCCMD	<a href="#">17</a>
XDCCMDA	<a href="#">17</a>
XDCHELPM	<a href="#">17</a>
XDCINIT proc!	<a href="#">38</a>
XDCIVP	<a href="#">17</a>
XDCMAPS	<a href="#">17</a>
XDCONLHG	<a href="#">17</a>
XDCSYMED	<a href="#">17</a>
XDCTFS	<a href="#">17</a>
XDCXITS	<a href="#">17</a>
TFSATT21 default profile	
changing%	<a href="#">44</a>
TFSPROF table	<a href="#">23</a>
TFXDC31 table	<a href="#">23</a>
Top Secret (see CA-Top Secret)	
#	<a href="#">35</a>
trademarks notice	<a href="#">iii</a>
Unterse.jcl dataset	<a href="#">3</a>

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Index)**

usage warning .....	<u>ii</u>
user manuals	
Commands Reference# .....	<u>2</u>
Messages Reference# .....	<u>2</u>
Quick Reference .....	<u>2</u>
Release Guide .....	<u>2</u>
User's Guide .....	<u>2</u>
User's Guide manual .....	<u>2</u>
VTAMLST .....	<u>49</u>
web address (see internet) .....	<u>ii</u>
XDC	
installing its service SVC automatically0 .....	<u>39</u>
renaming .....	<u>15</u>
running without its service SVC' .....	<u>39</u>
XDC.AUTH resource .....	<u>30</u>
XDC.FASM resource .....	<u>30</u>
XDC.ZAP resource .....	<u>30</u>
XDC31	
target library .....	<u>17</u>
XDCACF2 dataset .....	<u>13</u>
XDCADATA library	
default MAPLIB# .....	<u>43</u>
XDCASM dataset .....	<u>13</u>
XDCCALL	
renaming .....	<u>16</u>
target library .....	<u>17</u>
XDCCALLA	
authorization .....	<u>20</u>
target library .....	<u>17</u>
XDCCDF dataset .....	<u>13</u>
XDCCLIST clist .....	<u>21</u> , <u>23</u>
XDCCLIST dataset .....	<u>13</u> , <u>21</u>
RECFM conversion% .....	<u>22</u>
XDCCMD	
target library .....	<u>17</u>
XDCCMDA	
authorization .....	<u>20</u>
target library .....	<u>17</u>
XDCCMDS dataset .....	<u>13</u> , <u>26</u>
XDCDLNK dataset .....	<u>13</u>
XDCDSRC dataset .....	<u>13</u>
XDCHELPM	
BDT warning .....	<u>20</u>
Bulk Data Transfer .....	<u>20</u>
copying .....	<u>15</u> , <u>20</u>
target library .....	<u>17</u>
XDCINIT job (see XDCINIT proc)	
# .....	<u>38</u>
XDCINIT proc	
Installing .....	<u>38</u>
renaming .....	<u>38</u>
running at IPL .....	<u>38</u>
target library .....	<u>38</u>
what it does .....	<u>39</u>
XDCIVP .....	<u>52</u>
target library .....	<u>17</u>
XDCJCL dataset .....	<u>13</u>
XDCJES2 dataset .....	<u>13</u>
XDCLBDEF clist .....	<u>22</u> - <u>24</u>
XDCLINK dataset .....	<u>13</u> , <u>18</u>

# ***z/XDC® z1.2 INSTALLATION GUIDE***

## **(Index)**

XDCM00 messages .....	<a href="#">23</a>
XDCMACS dataset .....	<a href="#">13</a>
XDCMAPS	
load module .....	<a href="#">43</a>
target library .....	<a href="#">17</a>
XDCMLIB dataset .....	<a href="#">13</a> , <a href="#">22</a>
XDCONLHG	
target library .....	<a href="#">17</a>
XDCPANEL panel .....	<a href="#">23</a> , <a href="#">24</a>
invoking .....	<a href="#">24</a>
XDCPHELP panel .....	<a href="#">23</a>
XDCPHLPx panels .....	<a href="#">23</a>
XDCPLIB dataset .....	<a href="#">13</a> , <a href="#">22</a>
XDCPLPA dataset .....	<a href="#">13</a> , <a href="#">18</a>
XDCSYMED	
target library .....	<a href="#">17</a>
XDCT31A panel .....	<a href="#">23</a>
XDCT31B panel .....	<a href="#">23</a>
XDCTFS	
target library .....	<a href="#">17</a>
XDCTLIB dataset .....	<a href="#">13</a> , <a href="#">22</a>
XDCXITS	
target library .....	<a href="#">17</a>
Xdcz12.zip dataset .....	<a href="#">1</a>
Xmitlib.trs dataset .....	<a href="#">2</a> , <a href="#">3</a>
ZAP resource (see XDC.ZAP resource)	
( .....	<a href="#">30</a>
zapping .....	<a href="#">30</a>

# ***z/XDC® z1.2 INSTALLATION GUIDE***

